

Elastic Volume Service

User Guide

Issue 08

Date 2019-06-30



Copyright © Huawei Technologies Co., Ltd. 2021. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions

HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Contents

1 Disk Capacity Expansion	1
1.1 Expansion Overview	1
1.2 Expanding Capacity for an In-use EVS Disk	3
1.3 Expanding Capacity for an Available EVS Disk	6
1.4 Extending Disk Partitions and File Systems (Windows Server 2008)	7
1.5 Extending Disk Partitions and File Systems (Linux)	
1.5.1 Partition and File System Extension Preparations (Linux)	
1.5.2 Extending Partitions and File Systems for System Disks (Linux)	
1.5.3 Extending Partitions and File Systems for Data Disks (Linux)	44
2 Detaching an EVS Disk	57
2.1 Detaching a System Disk	57
2.2 Detaching a Data Disk	58
3 Attaching an Existing Disk	60
3.1 Attaching an Existing System Disk	60
3.2 Attaching an Existing Non-Shared Disk	61
3.3 Attaching an Existing Shared Disk	62
4 Deleting an EVS Disk	64
5 Viewing Disk Details	66
6 Managing an Encrypted EVS Disk	68
7 Managing a Shared EVS Disk	70
8 Managing EVS Backup	72
9 Managing Snapshots (OBT)	75
9.1 Snapshot Overview (OBT)	
9.2 Creating a Snapshot (OBT)	76
9.3 Deleting a Snapshot (OBT)	77
9.4 Viewing Details of a Snapshot (OBT)	78
9.5 Rolling Back Data from a Snapshot (OBT)	
9.6 Creating an EVS Disk from a Snapshot (OBT)	79
10 Managing EVS Disk Transfer	81

11 Managing a Tag	84
11.1 Tag Overview	84
11.2 Adding a Tag	84
11.3 Modifying a Tag	
11.4 Deleting a Tag	86
11.5 Searching Disks by Tags	86
12 Changing Disk Name	88
13 Viewing EVS Monitoring Data	90
14 Querying EVS Traces	94
15 Managing Quotas	95
15.1 Querying EVS Resource Quotas	95
15.2 Increasing EVS Resource Quotas	
A Appendix	97
A.1 EVS Disk Status	97
A.2 EVS Snapshot Status	
B Change History	101

Disk Capacity Expansion

1.1 Expansion Overview

What Is Capacity Expansion?

If the capacity of an existing disk is insufficient, you can expand the disk capacity to increase the storage space.

Both system disks and data disks can be expanded. A system disk can be expanded to up to 1 TB, and a data disk to 32 TB. Currently, disk capacities can be expanded only. Capacity reduction is not supported.

How to Expand the Disk Capacity?

A capacity expansion operation includes the following steps:

- 1. Expand the disk capacity on the management console.
- 2. Log in to the server and extend the disk partition and file system.




Figure 1-1 Capacity expansion procedure

Expand the Disk Capacity on the Management Console

Choose a proper expansion method based on the disk status. For how to view the disk status, see **5 Viewing Disk Details**.

For an In-use disk:

The disk has been attached to a server. Check whether the disk can be expanded in the In-use state by referring to **Constraints**.

- If yes, expand the disk capacity according to 1.2 Expanding Capacity for an In-use EVS Disk.
- If no, detach the disk. Then, expand the disk capacity according to 1.3
 Expanding Capacity for an Available EVS Disk.
- For an Available disk:

The disk has not been attached to any server and can be directly expanded by referring to 1.3 Expanding Capacity for an Available EVS Disk.

A shared disk can be expanded only when its status is **Available**.

Log In to the Server and Extend the Disk Partition and File System

After the disk has been expanded on the management console, only the disk storage capacity is enlarged, but its additional space cannot be used directly. You

must log in to the server and extend the disk partition and file system. For details, see **Table 1-1**.

Table 1-1 Extending the disk partition and file system

Capacity After Expansion	Extend Disk Partition and File System
Disk capacity ≤2 TB	Windows: 1.4 Extending Disk Partitions and File Systems (Windows Server 2008)
	• Linux: 1.5.1 Partition and File System Extension Preparations (Linux)
Disk capacity >2 TB	 GPT partition style: 1.4 Extending Disk Partitions and File Systems (Windows Server 2008) or 1.5.1 Partition and File System Extension Preparations (Linux)
	MBR partition style: Not supported The maximum disk capacity that MBR supports is 2 TB, and the disk space exceeding 2 TB cannot be used. If your disk uses MBR and you need to expand the disk capacity to over 2 TB, change the partition style from MBR to GPT. Ensure that the disk data has been backed up before changing the partition style because services will be interrupted and data on the disk will be cleared during this change.

□ NOTE

If the server is stopped during the expansion, the additional space of a Windows system disk, Windows data disk, and Linux system disk may be automatically added to the end partition after the server is started. In this case, the additional space can be directly used. If the additional space is not automatically added, extend the partition and file system according to the preceding steps.

Related Operations

For more expansion FAQs, see **Disk Capacity Expansion FAQs**.

1.2 Expanding Capacity for an In-use EVS Disk

Scenarios

This topic describes how to expand the capacity of an In-use EVS disk on the management console. The In-use status indicates that the disk has been attached

to a server. You do not need to detach the disk when expanding an In-use disk. For how to view the disk status, see **5 Viewing Disk Details**.

Constraints

- Currently, disk capacities can only be expanded, but cannot be reduced.
- When expanding an In-use disk, the server containing this disk must be in the **Running** or **Stopped** state.
- A shared disk cannot be expanded in the In-use state. To expand a shared In-use disk, you must detach it from all its servers, wait until its status changes to Available, and then expand its capacity. For more information, see 1.3
 Expanding Capacity for an Available EVS Disk.
- Only some server OSs support capacity expansion of In-use disks. If the server
 OS does not support capacity expansion of In-use disks, detach the disk and
 then expand its capacity. Otherwise, you may need to stop and then start the
 server after the expansion to make the expansion takes effect.
 - Perform the following operations to check whether your server OS support capacity expansion of In-use disks:
 - a. Both public images and private images listed on the console support the capacity expansion of In-use disks.
 - Log in to the management console and choose **Image Management Service**. On the **Public Images** tab, view the images of the **ECS image** type.
 - b. If your server OS does not appear in the image list, check whether it is included in **Table 1-2**.
 - If your server OS appears in **Table 1-2**, the OS supports capacity expansion of In-use disks. Otherwise, you must detach the disk and then expand its capacity. For details, see **1.3 Expanding Capacity for an Available EVS Disk**.

Table 1-2 OSs that support the capacity expansion of In-use disks

os	Version
CentOS 7	7.2 64 bit or later
CentOS 6	6.5 64 bit or later
Debian	8.5.0 64 bit or later
Fedora	24 64 bit or later
SUSE 12	SUSE Linux Enterprise Server 12 64bit or later
SUSE 11	SUSE Linux Enterprise Server 11 SP4 64bit
OpenSUSE	42.1 64bit or later
Oracle Linux Server release 7	7.2 64bit or later
Oracle Linux Server release 6	6.7 64bit or later

OS	Version
Ubuntu Server 16	16.04 64bit
Ubuntu Server 14	14.04 64-bit and 14.04.4 64-bit
Windows Server 2016	Windows Server 2016 R2 Enterprise 64bit
Windows Server 2012	Windows Server 2012 R2 Standard 64bit
Windows Server 2008	Windows Server 2008 R2 Enterprise 64bit
Red Hat Enterprise Linux 7	7.3 64bit
Red Hat Enterprise Linux 6	6.8 64bit

Prerequisites

You have backed up the disk data by creating a backup or snapshot. For more information about disk backups, see **8 Managing EVS Backup**. For more information about snapshots, see **9.2 Creating a Snapshot (OBT)**.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

- **Step 3** Determine whether to view the server information before expanding the disk.
 - If you need to view the server information, perform the following procedure:
 - a. In the disk list, click the name of the to-be-expanded disk.

 The disk details page is displayed.
 - b. Click the **Servers** tab to view the server where the target disk has been attached.
 - c. Click **Expand Capacity** in the upper right corner of the page. The expansion page is displayed.
 - If you do not need to view the server information, perform the following procedure:
 - a. In the disk list, locate the row that contains the target disk and click **Expand Capacity** in the **Operation** column.

The expansion page is displayed.

- **Step 4** Set the **Add Capacity (GB)** parameter and click **Next**.
- **Step 5** On the **Details** page, check the disk information again.
 - If you do not need to modify the specifications, click **Submit** to start the expansion.

• If you need to modify the specifications, click **Previous** to modify parameters.

After the specifications are submitted, go back to the disk list page.

- **Step 6** In the displayed dialog box, click **OK**.
- **Step 7** In the disk list, view the capacity of the target disk.

When the disk status changes from **Expanding** to **In-use** and the disk capacity increases, the expansion has succeeded.

◯ NOTE

When the disk status is **Expanding**, you cannot change the specifications of the ECS where the disk attached.

Step 8 After a disk has been expanded on the management console, only the disk storage capacity is enlarged, but its additional space cannot be used directly. You must log in to the server and extend the disk partition and file system.

The operation method varies depending on the server OS.

- In Windows, see 1.4 Extending Disk Partitions and File Systems (Windows Server 2008).
- In Linux, see 1.5.1 Partition and File System Extension Preparations (Linux).

----End

1.3 Expanding Capacity for an Available EVS Disk

Scenarios

This topic describes how to expand the capacity of an Available EVS disk on the management console. The Available status indicates that the disk has not been attached to any server. For how to view the disk status, see 5 Viewing Disk Details.

Constraints

- Currently, disk capacities can only be expanded, but cannot be reduced.
- A shared disk cannot be expanded in the In-use state. To expand a shared In-use disk, you must detach it from all its servers, wait until its status changes to Available, and then expand its capacity.

Prerequisites

You have backed up the disk data by creating a backup or snapshot. For more information about disk backups, see **8 Managing EVS Backup**. For more information about snapshots, see **9.2 Creating a Snapshot (OBT)**.

Procedure

Step 1 Log in to the management console.

Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

Step 3 In the disk list, locate the row that contains the target disk and click **Expand Capacity** in the **Operation** column.

The expansion page is displayed.

- **Step 4** Set the **Add Capacity (GB)** parameter and click **Next**.
- **Step 5** On the **Details** page, check the disk information again.
 - If you do not need to modify the specifications, click **Submit** to start the expansion.
 - If you need to modify the specifications, click **Previous** to modify parameters.

After the specifications are submitted, go back to the disk list page.

Step 6 In the disk list, view the capacity of the target disk.

When the disk status changes from **Expanding** to **Available** and the disk capacity increases, the expansion has succeeded.

- **Step 7** Attach the disk to the server. For details, see the following topics:
 - 3.1 Attaching an Existing System Disk
 - 3.2 Attaching an Existing Non-Shared Disk
 - 3.3 Attaching an Existing Shared Disk
- **Step 8** After a disk has been expanded on the management console, only the disk storage capacity is enlarged, but its additional space cannot be used directly. You must log in to the server and extend the disk partition and file system.

The operation method varies depending on the server OS.

- In Windows, see 1.4 Extending Disk Partitions and File Systems (Windows Server 2008).
- In Linux, see 1.5.1 Partition and File System Extension Preparations (Linux).

----End

1.4 Extending Disk Partitions and File Systems (Windows Server 2008)

Scenarios

After a disk has been expanded on the management console, the disk size is enlarged, but the additional space cannot be used directly.

In Windows, you must allocate the additional space to an existing partition or a new partition.

If the disk capacity is expanded on a stopped server, the additional space of a Windows system disk or Windows data disk will be automatically added to the

partition at the end of the disk upon the server startup. In this case, the additional space can be used directly.

This topic uses Windows Server 2008 R2 Enterprise 64bit as the sample OS to describe the expansion methods:

- For a system disk:
 - If volume (C:) already exists, you can add the additional space to volume
 (C:) and use it as a system volume. For details, see System Disk: Add Additional Space to Volume (C:).
 - If volume (C:) already exists, you can create a new volume such as volume (F:) with the additional space and use the new volume as a data volume. For details, see System Disk: Create New Volume (F:) with Additional Space.
 - If the additional space has been added to volume (C:), you can shrink volume (C:), create a new volume with the available space, and use the new volume as a data volume. Only the available space can be shrunk and used to create the new volume. The additional space cannot be shrunk if it has already been used. This topic uses a system disk to describe how to perform extension operations for a Windows disk. These operations are also suitable for data disks. For details, see System Disk: Add Additional Space to Volume (C:) and Allocate Available Space to New Volume (D:) via the Shrink Function.
- For a data disk:
 - If volume (D:) already exists, you can add the additional space to volume (D:) and use it as a data volume. For details, see Data Disk: Add Additional Space to Volume (D:).
 - If volume (D:) already exists, you can create a new volume such as volume (E:) with the additional space and use the new volume as a data volume. For details, see Data Disk: Create New Volume (E:) with Additional Space.

The method for allocating the additional space varies with the server OS. This topic is used for reference only. For detailed operations and differences, see the corresponding OS documents.

NOTICE

Performing the expansion operations with caution. Misoperation may lead to data loss or exceptions. Therefore, you are advised to back up the disk data using backups or snapshots before expansion. For details about backups, see 8

Managing EVS Backup. For details about snapshots, see 9.2 Creating a Snapshot (OBT).

Prerequisites

- You have expanded the disk capacity and attached the disk to a server on the management console. For details, see 1.2 Expanding Capacity for an In-use EVS Disk or 1.3 Expanding Capacity for an Available EVS Disk.
- You have logged in to the server.

- For how to log in to an ECS, see Logging In to an ECS.
- For how to log in to a BMS, see Logging In to the BMS.

System Disk: Add Additional Space to Volume (C:)

In this example, the system disk has 50 GB originally, and 22 GB is added on the management console. The following procedure describes how to add this 22 GB to volume (C:) on the server. After the operation is complete, volume (C:) will have 72 GB of capacity and can be used as a system volume.


Step 1 On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

Step 2 In the navigation tree, choose **Storage** > **Disk Management**.

The **Disk Management** window is displayed.

Figure 1-2 Disk Management (system disk)



MOTE

If you cannot view the additional space, right-click **Disk Management** and choose **Refresh** from the shortcut menu.

- **Step 3** On the **Disk Management** page, select the disk and volume that you want to extend. The current volume size and unallocated space are displayed.
- **Step 4** Right-click the target volume and choose **Extend Volume**.




Figure 1-3 Choosing Extend Volume

Step 5 On the displayed Extend Volume Wizard window, click Next.




Figure 1-4 Extend Volume Wizard

Step 6 In the text box to the right of **Select the amount of space in MB**, enter the amount of the additional space and click **Next**.

File Actor Wew Help

For Action Wew Help

For Actio

Figure 1-5 Selecting space

Step 7 Click Finish.

After the expansion succeeded, the partition size is larger than the original size.




Figure 1-6 Capacity expansion succeeded

----End

System Disk: Create New Volume (F:) with Additional Space

In this example, the system disk has 40 GB originally, and 60 GB is added on the management console. The following procedure describes how to use this 60 GB to create a new volume, for example volume (F:), on the server. After the operation is complete, new volume (F:) has 60 GB of capacity and can be used as a data volume.


Step 1 On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

Step 2 In the navigation tree, choose **Storage** > **Disk Management**.

The **Disk Management** window is displayed.

Figure 1-7 Refresh (system disk)



Step 3 If you cannot view the additional space, right-click **Disk Management** and choose **Refresh** from the shortcut menu.

After the refresh, the additional space is displayed in the right area and is unallocated.




Figure 1-8 Unallocated disk space (system disk)

Step 4 In the **Unallocated** area of **Disk 0**, right-click the blank area and choose **New Simple Volume**.




Figure 1-9 New Simple Volume (system disk)

Step 5 On the displayed New Simple Volume Wizard window, click Next.




Figure 1-10 New Simple Volume Wizard (system disk)

Step 6 On the displayed **Specify Volume Size** page, set **Simple volume size in MB** and click **Next**. In this example, the default size is used.






Figure 1-11 Specify Volume Size (system disk)

Step 7 On the displayed **Assign Drive Letter and Path** page, click **Assign the following drive letter**, select a drive letter, and click **Next**. In this example, drive letter **F** is selected.





Step 8 On the displayed **Format Partition** page, click **Format this volume with the following settings**, set parameters based on the requirements, and select **Perform a quick format**. Then, click **Next**.




Figure 1-13 Format Partition (system disk)

Step 9 Click Finish.

After the expansion succeeded, new volume (F:) is displayed.




Figure 1-14 Completing the New Simple Volume Wizard (new volume F:)




Figure 1-15 New Volume (F:)

----End

System Disk: Add Additional Space to Volume (C:) and Allocate Available Space to New Volume (D:) via the Shrink Function

In this example, the system disk has 40 GB originally, and 60 GB is added on the management console and then formatted and added to volume (C:). This 60 GB has not been used.

The following procedure describes how to use the shrink function to create new volume (D:) with this 60 GB. After the operation is complete, new volume (D:) can be used as a data volume.

Step 1 On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

Step 2 In the navigation tree, choose **Storage** > **Disk Management**.

The **Disk Management** window is displayed.




Figure 1-16 Refresh (shrink volume)

Figure 1-17 Shrink Volume

Step 3 In the (C:) area of Disk 0, right-click the blank area and choose Shrink Volume.



Server Manager (ECS-0514-FQY


Description
Configuration
Storage
Windows Server Backup
Disk Management □ Disk 0 (C:) 99.90 GB NTFS Healthy (Boot, Page File, Crash Dump, Primary Partition) Basic 100.00 GB Online Mark Partition as Active Properties ■ Unallocated ■ Primary partition

Step 4 The system automatically queries the available shrink space. In the displayed dialog box, enter the available space and click Shrink.

_ B ×


In this example, the volume available space is 60 GB. Therefore, enter **61440** (60×1024 MB).

Figure 1-18 Shrink (shrink volume)




After the operation is complete, **Disk 0** has 60 GB unallocated space.

Figure 1-19 Unallocated (shrink volume)




Step 5 In the **Unallocated** area of **Disk 0**, right-click the blank area and choose **New Simple Volume**.

Figure 1-20 New Simple Volume (shrink volume)




Step 6 On the displayed New Simple Volume Wizard window, click Next.

Figure 1-21 New Simple Volume Wizard (shrink volume)



Step 7 On the displayed **Specify Volume Size** page, set **Simple volume size in MB** and click **Next**. In this example, the default size is used.





Step 8 On the displayed **Assign Drive Letter and Path** page, click **Assign the following drive letter**, select a drive letter, and click **Next**. In this example, drive letter **D** is selected.




Figure 1-23 Assign Driver Letter or Path (shrink volume)

Step 9 On the displayed **Format Partition** page, click **Format this volume with the following settings**, set parameters based on the requirements, and select **Perform a quick format**. Then, click **Next**.





Figure 1-24 Format Partition (shrink volume)

Step 10 Click Finish.

After the expansion succeeded, new volume (D:) is displayed.

Figure 1-25 Completing the New Simple Volume Wizard (new volume D:)






Figure 1-26 New Volume (D:)

----End

Data Disk: Add Additional Space to Volume (D:)

In this example, the data disk has 100 GB originally, and 50 GB is added on the management console. The following procedure describes how to add this 50 GB to volume (D:) on the server. After the operation is complete, volume (D:) has 150 GB of capacity and can be used as a data volume.

Step 1 On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

Step 2 In the navigation tree, choose **Storage** > **Disk Management**.

The **Disk Management** window is displayed.




Figure 1-27 Disk Management (data disk)

■ NOTE

If you cannot view the additional space, right-click **Disk Management** and choose **Refresh** from the shortcut menu.

- **Step 3** On the **Disk Management** page, select the disk and volume that you want to extend. The current volume size and unallocated space are displayed.
- **Step 4** Right-click the target volume and choose **Extend Volume**.




Figure 1-28 Choosing Extend Volume (Windows Server 2008)

Step 5 On the displayed **Extend Volume Wizard** window, click **Next**.






Figure 1-29 Extend Volume Wizard (Windows Server 2008)

Step 6 In the text box to the right of **Select the amount of space in MB**, enter the amount of the additional space and click **Next**.





Step 7 Click Finish.

After the expansion succeeded, the partition size is larger than the original size.




Figure 1-31 Capacity expansion succeeded (Windows Server 2008)

----End

Data Disk: Create New Volume (E:) with Additional Space

In this example, the data disk has 40 GB originally, and 60 GB is added on the management console. The following procedure describes how to use this 60 GB to create a new volume, for example volume (E:), on the server. After the operation is complete, new volume (E:) has 60 GB of capacity and can be used as a data volume.

Step 1 On the desktop of the server, right-click **Computer** and choose **Manage** from the shortcut menu.

The **Server Manager** window is displayed.

Step 2 In the navigation tree, choose **Storage** > **Disk Management**.

The **Disk Management** window is displayed.




Figure 1-32 Refresh (data disk)

Step 3 If you cannot view the additional space, right-click **Disk Management** and choose **Refresh** from the shortcut menu.

After the refresh, the additional space is displayed in the right area and is unallocated.






Figure 1-33 Unallocated disk space (data disk)


Step 4 In the **Unallocated** area of **Disk 1**, right-click the blank area and choose **New Simple Volume**.

Figure 1-34 New Simple Volume (data disk)





Step 5 On the displayed New Simple Volume Wizard window, click Next.





Step 6 On the displayed **Specify Volume Size** page, set **Simple volume size in MB** and click **Next**. In this example, the default size is used.





Step 7 On the displayed **Assign Drive Letter and Path** page, click **Assign the following drive letter**, select a drive letter, and click **Next**. In this example, drive letter **E** is selected.





Figure 1-37 Assign Driver Letter or Path (data disk)

Step 8 On the displayed **Format Partition** page, click **Format this volume with the following settings**, set parameters based on the requirements, and select **Perform a quick format**. Then, click **Next**.

Figure 1-38 Format Partition (data disk)



Step 9 Click Finish.

After the expansion succeeded, new volume (E:) is displayed.





Figure 1-39 Completing the New Simple Volume Wizard (new volume E:)

Figure 1-40 New Volume (E:)



----End

1.5 Extending Disk Partitions and File Systems (Linux)

1.5.1 Partition and File System Extension Preparations (Linux)

Before extending the disk partition and file system, you must check the disk partition style and file system format, and then select the appropriate operation accordingly.

- 1. To view the disk partition style, see the following methods:
 - Method 1: Check Partition Style and File System Format Using fdisk
 - Method 2: Check Partition Style and File System Format Using parted
- 2. To extend disk partitions and file systems, see Table 1-3.

NOTICE

The following operation guide applies only to the Linux OS whose kernel version is 3.6.0 or later.

You can run **uname -a** to check the kernel version of the Linux OS. If the kernel version is earlier than 3.6.0, see **Partition and File System Extension Preparations (Linux)**.

Table 1-3 Disk partition and file system extension scenarios

Disk	Scenario	Method
Syste m disk	Allocate the additional space to an existing MBR partition.	Extending an Existing MBR Partition
	Create a new MBR partition with the additional space.	Creating a New MBR Partition
Data disk	Allocate the additional space to an existing MBR partition.	Extending an Existing MBR or GPT Partition
	Create a new MBR partition with the additional space.	Creating a New MBR Partition
	Allocate the additional space to an existing GPT partition.	Extending an Existing MBR or GPT Partition
	Create a new GPT partition with the additional space.	Creating a New GPT Partition

The maximum disk capacity that MBR supports is 2 TB, and the disk space exceeding 2 TB cannot be used.

If your disk uses MBR and you need to expand the disk capacity to over 2 TB, change the partition style from MBR to GPT. Ensure that the disk data has been backed up before changing the partition style because services will be interrupted and data on the disk will be cleared during this change.

Method 1: Check Partition Style and File System Format Using fdisk

Step 1 Run the following command to view all the disks attached to the server:

lsblk

Information similar to the following is displayed:

In this example, data disk /dev/vdb already has partition /dev/vdb1 before capacity expansion, and the additional 50 GB added has not been allocated yet. Therefore, /dev/vdb has 150 GB, and /dev/vdb1 has 100 GB.

Step 2 Run the following command to view the current disk partition style:

fdisk -l

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# fdisk -l
Disk /dev/vda: 42.9 GB, 42949672960 bytes, 83886080 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000bcb4e
 Device Boot
                                   Blocks Id System
                 Start
                           End
/dev/vda1 *
                 2048 83886079 41942016 83 Linux
Disk /dev/vdb: 161.1 GB, 161061273600 bytes, 314572800 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x38717fc1
 Device Boot
                 Start
                           End
                                   Blocks Id System
/dev/vdb1
                 2048 209715199 104856576 83 Linux
```

The value in the **System** column indicates the disk partition style. Value **Linux** indicates the MBR partition style. Value **GPT** indicates the GPT partition style.

If the disk partitions displayed are inconsistent with those obtained in Step 1, the partition that is not displayed uses the GPT partition style and has unallocated space. In this case, you cannot query all the partition information using the fdisk -l command. Go to Method 2: Check Partition Style and File System Format Using parted.

- If the disk partitions displayed are consistent with those obtained in Step 1, continue with the following operations.
- **Step 3** Run the following command to view the partition's file system format:

blkid Disk partition

In this example, run the following command:

blkid /dev/vdb1

In the command output, the **TYPE** value is **ext4**, indicating that **/dev/vdb1**'s file system format is **ext4**.

Step 4 Run the following command to view the file system status:

ext*: e2fsck -n Disk partition

xfs: xfs_repair -n Disk partition

In this example, the ext4 file system is used. Therefore, run the following command:

e2fsck -n /dev/vdb1

Information similar to the following is displayed:

[root@ecs-test-0001 ~]# e2fsck -n /dev/vdb1 e2fsck 1.42.9 (28-Dec-2013)
Warning! /dev/vdb1 is mounted.
Warning: skipping journal recovery because doing a read-only filesystem check. /dev/vdb1: clean, 11/6553600 files, 459544/26214144 blocks

If the file system status is **clean**, the file system status is normal. Otherwise, rectify the faulty and then perform the capacity expansion.

----End

Method 2: Check Partition Style and File System Format Using parted

Step 1 Run the following command to view all the disks attached to the server:

lsblk

Information similar to the following is displayed:

[root@ecs-test-0001 ~]# lsblk

NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda 253:0 0 40G 0 disk

__vda1 253:1 0 40G 0 part /
vdb 253:16 0 150G 0 disk

__vdb1 253:17 0 100G 0 part /mnt/sdc

In this example, data disk /dev/vdb already has partition /dev/vdb1 before capacity expansion, and the additional 50 GB added has not been allocated yet. Therefore, /dev/vdb has 150 GB, and /dev/vdb1 has 100 GB.

Step 2 Run the following command and enter **p** to view the disk partition style:

parted Disk

For example, run the following command to view /dev/vdb's partition style:

parted /dev/vdb

```
[root@ecs-test-0001 ~]# parted /dev/vdb
GNU Parted 3.1
Using /dev/vdb
Welcome to GNU Parted! Type 'help' to view a list of commands.
(parted) p
Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that another
operating system believes the
disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?
Fix/Ignore/Cancel? Fix
Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all of
the space (an extra 104857600
blocks) or continue with the current setting?
Fix/Ignore? Fix
Model: Virtio Block Device (virtblk)
Disk /dev/vdb: 161GB
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start End Size File system Name Flags
     1049kB 107GB 107GB ext4
                                        test
(parted)
```

In the command output, parameter **Partition Table** indicates the disk partition style. Value **msdos** indicates the MBR partition style, and value **gpt** indicates the GPT partition style.

• If the following error information is displayed, enter **Fix**.

Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that another operating system believes the disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?

The GPT partition table information is stored at the start of the disk. To reduce the risk of damage, a backup of the information is saved at the end of the disk. When you expand the disk capacity, the end of the disk changes accordingly. In this case, enter **Fix** to move the backup file of the information to new disk end.

If the following warning information is displayed, enter Fix.
 Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all of the space (an extra 104857600 blocks) or continue with the current setting?
 Fix/Ignore? Fix

Enter **Fix** as prompted. The system automatically sets the GPT partition style for the additional space.

Step 3 Enter **q** and press **Enter** to exit parted.

----End

1.5.2 Extending Partitions and File Systems for System Disks (Linux)

Scenarios

After a disk has been expanded on the management console, the disk size is enlarged, but the additional space cannot be used directly.

In Linux, you must allocate the additional space to an existing partition or a new partition.

If the disk capacity is expanded when its server is stopped, the additional space of a Linux system disk will be automatically added to the partition at the disk end upon the server startup. In this case, the additional space can be used directly.

This topic uses CentOS 7.4 64bit to describe how to extend the disk partition using growpart and fdisk. The method is used for ECS only. The method for allocating the additional space varies with the server OS. This example is used for reference only. For detailed operations and differences, see the corresponding OS documents.

For how to extend the partitions and file systems on a BMS system disk, see **How Do I Increase the Size of the Root Partition of a BMS Which Is Quickly Provisioned?**

- Extending an Existing MBR Partition
- Creating a New MBR Partition

NOTICE

Performing the expansion operations with caution. Misoperation may lead to data loss or exceptions. Therefore, you are advised to back up the disk data using backups or snapshots before expansion. For details about backups, see 8 Managing EVS Backup. For details about snapshots, see 9.2 Creating a Snapshot (OBT).

Prerequisites

- You have expanded the disk capacity and attached the disk to a server on the management console. For details, see 1.2 Expanding Capacity for an In-use EVS Disk or 1.3 Expanding Capacity for an Available EVS Disk.
- You have logged in to the server.
 - For how to log in to an ECS, see Logging In to an ECS.
 - For how to log in to a BMS, see **Logging In to the BMS**.
- The kernel version of the Linux OS is 3.6.0 or later.

You can run **uname** -a to check the kernel version of the Linux OS. If the kernel version is earlier than 3.6.0, see **Partition and File System Extension Preparations (Linux)**.

Extending an Existing MBR Partition

CentOS 7.4 64bit is used as the sample OS. Originally, system disk /dev/vda has 40 GB and one partition (/dev/vda1), and then 60 GB is added to the disk. The following procedure shows you how to allocate the additional 60 GB to the existing MBR partition /dev/vda1.

Step 1 (Optional) Run the following command to install the growpart tool:

yum install cloud-utils-growpart

■ NOTE

You can run the **growpart** command to check whether the growpart tool has been installed. If the command output displays the tool usage instructions, the tool has been installed and you do not need to install it separately.

Step 2 Run the following command to view the total capacity of the **/dev/vda** system disk:

fdisk -l

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# fdisk -l

Disk /dev/vda: 107.4 GB, 107374182400 bytes, 209715200 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dos

Disk identifier: 0x000bcb4e

Device Boot Start End Blocks Id System

/dev/vda1 * 2048 83886079 41942016 83 Linux
```

Step 3 Run the following command to view the capacity of the /dev/vda1 partition:

df -TH

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# df -TH
                   Size Used Avail Use% Mounted on
Filesystem
           Type
/dev/vda1
            ext4 43G 2.0G 39G 5% /
devtmpfs 2.0G 0 2.0G 0% /dev
devtmpfs
           tmpfs 2.0G 0 2.0G 0% /dev/shm
tmnfs
tmpfs
           tmpfs
                   2.0G 9.0M 2.0G 1% /run
tmpfs
           tmpfs
                   2.0G 0 2.0G 0% /sys/fs/cgroup
           tmpfs 398M 0 398M 0% /run/user/0
tmpfs
```

Step 4 Run the following command to extend the partition using growpart:

growpart System disk Partition number

In this example, run the following command:

growpart /dev/vda 1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# growpart /dev/vda 1 CHANGED: partition=1 start=2048 old: size=83884032 end=83886080 new: size=209713119,end=209715167
```

Step 5 Run the following command to extend the file system of the partition:

resize2fs Disk partition

In this example, run the following command:

resize2fs /dev/vda1

```
[root@ecs-test-0001 ~]# resize2fs /dev/vda1 resize2fs 1.42.9 (28-Dec-2013)
Filesystem at /dev/vda1 is mounted on /; on-line resizing required old_desc_blocks = 5, new_desc_blocks = 13
The filesystem on /dev/vda1 is now 26214139 blocks long.
```

Step 6 Run the following command to view the new capacity of the /dev/vda1 partition:

df -TH

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# df -TH
                   Size Used Avail Use% Mounted on
Filesystem
           Type
/dev/vda1
           ext4
                   106G 2.0G 99G 2% /
           devtmpfs 2.0G 0 2.0G 0% /dev
devtmpfs
           tmpfs 2.0G 0 2.0G 0% /dev/shm
tmpfs 2.0G 9.0M 2.0G 1% /run
tmpfs
tmpfs
           tmpfs 2.0G 0 2.0G 0% /sys/fs/cgroup
tmpfs
           tmpfs 398M 0 398M 0% /run/user/0
tmpfs
```

----End

Creating a New MBR Partition

Originally, system disk /dev/vda has 40 GB and one partition (/dev/vda1), and then 40 GB is added to the disk. The following procedure shows you how to create a new MBR partition /dev/vda2 with this 40 GB.

Step 1 Run the following command to view the disk partition information:

fdisk -l

Information similar to the following is displayed:

```
[root@ecs-2220 ~]# fdisk -l
Disk /dev/vda: 85.9 GB, 85899345920 bytes, 167772160 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x0008d18f
 Device Boot
                Start
                           End
                                 Blocks Id System
                2048 83886079 41942016 83 Linux
/dev/vda1 *
```

In the command output, the capacity of the **dev/vda** system disk is 80 GB, in which the in-use dev/vda1 partition takes 40 GB and the additional 40 GB has not been allocated.

Step 2 Run the following command to enter fdisk:

fdisk /dev/vda

Information similar to the following is displayed:

```
[root@ecs-2220 ~]# fdisk /dev/vda
Welcome to fdisk (util-linux 2.23.2).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.
Command (m for help):
```

Step 3 Enter **n** and press **Enter** to create a new partition.

```
Command (m for help): n
Partition type:
 p primary (1 primary, 0 extended, 3 free)
 e extended
```

There are two types of disk partitions:

- Choosing p creates a primary partition.
- Choosing **e** creates an extended partition.

If the MBR partition style is used, a maximum of 4 primary partitions, or 3 primary partitions and 1 extended partition can be created. The extended partition cannot be used directly and must be divided into logical partitions before use.

Disk partitions created using GPT are not categorized.

Step 4 In this example, a primary partition is created. Therefore, enter **p** and press **Enter** to create a primary partition.

Information similar to the following is displayed:

Select (default p): p Partition number (2-4, default 2):

Step 5 Partition number **2** is used in this example. Therefore, enter **2** and press **Enter**.

Information similar to the following is displayed:

Partition number (2-4, default 2): 2 First sector (83886080-167772159, default 83886080):

Step 6 Enter the new partition's start sector and press **Enter**. In this example, the default start sector is used.

The system displays the start and end sectors of the partition's available space. You can customize the value within this range or use the default value. The start sector must be smaller than the partition's end sector.

Information similar to the following is displayed:

First sector (83886080-167772159, default 83886080):
Using default value 83886080
Last sector, +sectors or +size{K,M,G} (83886080-167772159,default 167772159):

Step 7 Enter the new partition's end sector and press **Enter**. In this example, the default end sector is used.

The system displays the start and end sectors of the partition's available space. You can customize the value within this range or use the default value. The start sector must be smaller than the partition's end sector.

Information similar to the following is displayed:

Last sector, +sectors or +size{K,M,G} (83886080-167772159, default 167772159):
Using default value 167772159
Partition 2 of type Linux and of size 40 GiB is set

Command (m for help):

Step 8 Enter **p** and press **Enter** to view the new partition.

Information similar to the following is displayed:

Command (m for help): p

Disk /dev/vda: 85.9 GB, 85899345920 bytes, 167772160 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dos Disk identifier: 0x0008d18f

```
Device Boot Start End Blocks Id System
/dev/vda1 * 2048 83886079 41942016 83 Linux
/dev/vda2 83886080 167772159 41943040 83 Linux
Command (m for help):
```

Step 9 Enter **w** and press **Enter** to write the changes to the partition table.

Information similar to the following is displayed:

Command (m for help): w

The partition table has been altered!

Calling ioctl() to re-read partition table.

WARNING: Re-reading the partition table failed with error 16: Device or resource busy. The kernel still uses the old table. The new table will be used at the next reboot or after you run partprobe(8) or kpartx(8) Syncing disks.

The partition is created.

□ NOTE

In case that you want to discard the changes made before, you can exit fdisk by entering \mathbf{q} .

Step 10 Run the following command to synchronize the new partition table to the OS:

partprobe

Step 11 Run the following command to set the file system format for the new partition:

mkfs -t File system Disk partition

• Sample command of the ext* file system:

(The ext4 file system is used in this example.)

mkfs -t ext4 /dev/vda2

Information similar to the following is displayed:

[root@ecs-2220 ~]# mkfs -t ext4 /dev/vda2 mke2fs 1.42.9 (28-Dec-2013) Filesystem label= OS type: Linux Block size=4096 (log=2) Fragment size=4096 (log=2) Stride=0 blocks, Stripe width=0 blocks 2621440 inodes, 10485760 blocks 524288 blocks (5.00%) reserved for the super user First data block=0 Maximum filesystem blocks=2157969408 320 block groups 32768 blocks per group, 32768 fragments per group 8192 inodes per group Superblock backups stored on blocks: $32768,\,98304,\,163840,\,229376,\,294912,\,819200,\,884736,\,1605632,\,2654208,$

Allocating group tables: done Writing inode tables: done Creating journal (32768 blocks): done

Writing superblocks and filesystem accounting information: done Sample command of the xfs file system:

mkfs -t xfs /dev/vda2

4096000, 7962624

```
[root@ecs-2220 ~]# mkfs -t xfs /dev/vda2
meta-data=/dev/vda2 isize=512 agcount=4, agsize=2621440 blks
```

```
= sectsz=512 attr=2, projid32bit=1
= crc=1 finobt=0, sparse=0
data = bsize=4096 blocks=10485760, imaxpct=25
= sunit=0 swidth=0 blks
naming =version2 bsize=4096 ascii-ci=0 ftype=1
log =internal log bsize=4096 blocks=5120, version=2
= sectsz=512 sunit=0 blks, lazy-count=1
realtime =none extsz=4096 blocks=0, rtextents=0
```

The formatting takes a while, and you need to observe the system running status. Once **done** is displayed in the command output, the formatting is complete.

Step 12 (Optional) Run the following command to create a mount point:

Perform this step if you want to mount the partition on a new mount point.

mkdir Mount point

In this example, run the following command to create the **/opt** mount point:

mkdir /opt

Step 13 Run the following command to mount the new partition:

mount Disk partition Mount point

In this example, run the following command to mount the new partition /dev/vda2 on /opt:

mount /dev/vda2 /opt

□ NOTE

If the new partition is mounted on a directory that is not empty, the subdirectories and files in the directory will be hidden. Therefore, you are advised to mount the new partition on an empty directory or a new directory. If the new partition must be mounted on a directory that is not empty, move the subdirectories and files in this directory to another directory temporarily. After the partition is successfully mounted, move the subdirectories and files back.

Step 14 Run the following command to view the mount result:

df -TH

Information similar to the following is displayed:

```
[root@ecs-2220 ~]# df -TH
Filesystem Type
               Size Used Avail Use% Mounted on
/dev/vda1
         ext4
               43G 2.0G 39G 5% /
         devtmpfs 509M 0 509M 0% /dev
devtmpfs
        tmpfs 520M 0 520M 0% /dev/shm
tmpfs
        tmpfs 520M 7.2M 513M 2% /run
tmpfs
              tmpfs
        tmpfs
        tmpfs
tmpfs
/dev/vda2 ext4 43G 51M 40G 1% /opt
```

∩ NOTE

If the server is restarted, the mounting will become invalid. You can set automatic mounting for partitions at system start by modifying the /etc/fstab file. For details, see Setting Automatic Mounting at System Start.

----End

Setting Automatic Mounting at System Start

To automatically mount disk partitions at system start, do not specify partitions, for example /dev/vdb1, in /etc/fstab because the sequence of cloud devices, and therefore their names may change during the server stop and start. You are advised to use the universally unique identifier (UUID) in /etc/fstab to set automatic mounting at system start.

UUID is the unique character string for disk partitions in a Linux system.

Step 1 Run the following command to query the partition UUID:

blkid Disk partition

In this example, run the following command to query the UUID of the /dev/vdb1 partition:

blkid /dev/vdb1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# blkid /dev/vdb1
/dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4"
```

The UUID of the /dev/vdb1 partition is displayed.

Step 2 Run the following command to open the **fstab** file using the vi editor:

vi /etc/fstab

- **Step 3** Press **i** to enter the editing mode.
- **Step 4** Move the cursor to the end of the file and press **Enter**. Then, add the following information:

```
UUID=0b3040e2-1367-4abb-841d-ddb0b92693df /mnt/sdc ext4 defaults 0 2
```

The preceding content is used for reference only. Add the information that is used in the environment. The parameters are described as follows:

- The first column indicates the partition UUID obtained in **Step 1**.
- The second column indicates the directory on which the partition is mounted. You can guery the mount point using the **df-TH** command.
- The third column indicates the file system format of the partition. You can guery the file system format using the **df** -**TH** command.
- The fourth column indicates the partition mount option. Normally, this parameter is set to **defaults**.
- The fifth column indicates the Linux dump backup option.
 - **0**: not use Linux dump backup. Normally, dump backup is not used, and you can set this parameter to **0**.
 - 1: use Linux dump backup.
- The sixth column indicates the fsck option, that is, whether to use fsck to check the attached disk during startup.
 - 0: not use fsck.
 - If the mount point is the root partition (/), this parameter must be set to **1**.

When this parameter is set to **1** for the root partition, this parameter for other partitions must start with **2** so that the system checks the partitions in the ascending order of the values.

Step 5 Press **Esc**, enter :wq, and press **Enter**.

The system saves the configurations and exits the vi editor.

Step 6 Perform the following operations to verify the automatic mounting function:

1. Run the following command to unmount the partition:

umount Disk partition

In this example, run the following command:

umount /dev/vdb1

- Run the following command to reload all the content in the /etc/fstab file: mount -a
- 3. Run the following command to query the file system mounting information: **mount | grep** *Mount point*

In this example, run the following command:

mount | grep /mnt/sdc

If information similar to the following is displayed, the automatic mounting function takes effect:

root@ecs-test-0001 ~]# mount | grep /mnt/sdc /dev/vdb1 on /mnt/sdc type ext4 (rw,relatime,data=ordered)

----End

1.5.3 Extending Partitions and File Systems for Data Disks (Linux)

Scenarios

After a disk has been expanded on the management console, the disk size is enlarged, but the additional space cannot be used directly.

In Linux, you must allocate the additional space to an existing partition or a new partition.

This topic uses CentOS 7.4 64bit as the sample OS to describe how to extend an MBR or GPT partition. The method for allocating the additional space varies depending on the server OS. This document is used for reference only. For the detailed operations and differences, see the corresponding OS documents.

- Extending an Existing MBR or GPT Partition
- Creating a New MBR Partition
- Creating a New GPT Partition

NOTICE

Performing the expansion operations with caution. Misoperation may lead to data loss or exceptions. Therefore, you are advised to back up the disk data using backups or snapshots before expansion. For details about backups, see 8 Managing EVS Backup. For details about snapshots, see 9.2 Creating a Snapshot (OBT).

Prerequisites

- You have expanded the disk capacity and attached the disk to a server on the management console. For details, see 1.2 Expanding Capacity for an In-use EVS Disk or 1.3 Expanding Capacity for an Available EVS Disk.
- You have logged in to the server.
 - For how to log in to an ECS, see Logging In to an ECS.
 - For how to log in to a BMS, see **Logging In to the BMS**.
- The kernel version of the Linux OS is 3.6.0 or later.

You can run **uname -a** to check the kernel version of the Linux OS. If the kernel version is earlier than 3.6.0, see **Partition and File System Extension Preparations (Linux)**.

Extending an Existing MBR or GPT Partition

Originally, data disk /dev/vdb has 100 GB and one partition (/dev/vdb1), and then 50 GB is added to the disk. The following procedure shows you how to add this 50 GB to the existing MBR or GPT partition (/dev/vdb1).

Step 1 (Optional) Run the following command to install the growpart tool:

yum install cloud-utils-growpart

□ NOTE

You can run the **growpart** command to check whether the growpart tool has been installed. If the command output displays the tool usage instructions, the tool has been installed and you do not need to install it separately.

Step 2 (Optional) Run the following command to install the gdisk software package:

yum install gdisk

The following information is displayed:

Is this ok [y/d/N]:

Enter Y and press Enter to complete the installation.

Step 3 Run the following command to view the disk partition information:

fdisk -l

Information similar to the following is displayed:

[root@ecs-test-0001 ~]# fdisk -l

Disk /dev/vda: 42.9 GB, 42949672960 bytes, 83886080 sectors Units = sectors of 1 * 512 = 512 bytes

```
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000bcb4e
 Device Boot
                Start
                           End
                                  Blocks Id System
                2048 83886079 41942016 83 Linux
/dev/vda1 *
Disk /dev/vdb: 161.1 GB, 161061273600 bytes, 314572800 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x38717fc1
 Device Boot
                                  Blocks Id System
                Start
                           End
/dev/vdb1
                2048 209715199 104856576 83 Linux
```

Step 4 Run the following command to view the capacity of the /dev/vdb1 partition:

df -TH

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# df -TH
Filesystem
           Type Size Used Avail Use% Mounted on
           devtmpfs 509M 0 509M 0% /dev
devtmpfs
tmpfs
          tmpfs 520M 0 520M 0% /dev/shm
          tmpfs 520M 7.1M 513M 2% /run
tmpfs 520M 0 520M 0% /sys/fs
tmpfs
tmpfs
                  520M 0 520M 0% /sys/fs/cgroup
/dev/vda1
          ext4
                  43G 2.3G 38G 6% /
                  104M 0 104M 0% /run/user/0
tmpfs
          tmpfs
/dev/vdb1
          ext4
                  106G 63M 101G 1% /mnt/sdc
```

Step 5 Run the following command to extend the partition using growpart:

growpart Data disk Partition number

In this example, run the following command:

growpart /dev/vdb 1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# growpart /dev/vdb 1
CHANGED: partition=1 start=2048 old: size=209713152 end=209715200 new:
size=314570719,end=314572767
```

□ NOTE

If the following information is displayed:

```
no tools available to resize disk with 'gpt' FAILED: failed to get a resizer for id "
```

Install the gdisk software package according to Step 2.

- **Step 6** Extend the file system of the partition. The commands used for extending file systems vary.
 - For the **ext*** file system, run the following command:

resize2fs Disk partition

In this example, run the following command:

resize2fs /dev/vdb1

```
[root@ecs-test-0001 ~]# resize2fs /dev/vdb1
resize2fs 1.42.9 (28-Dec-2013)
Filesystem at /dev/vdb1 is mounted on /mnt/sdc; on-line resizing required
```

```
old_desc_blocks = 13, new_desc_blocks = 19
The filesystem on /dev/vdb1 is now 39321339 blocks long.
```

For the **xfs** file system, run the following command:

sudo xfs_growfs Disk partition

In this example, run the following command:

sudo xfs growfs /dev/vdb1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# sudo xfs growfs /dev/vdb1
                           isize=512 agcount=4, agsize=6553472 blks
meta-data=/dev/vdb1
                    sectsz=512 attr=2, projid32bit=1
                    crc=1
                             finobt=0 spinodes=0
     =
data
                     bsize=4096 blocks=26213888, imaxpct=25
                    sunit=0 swidth=0 blks
                         bsize=4096 ascii-ci=0 ftype=1
naming =version 2
     =internal
                       bsize=4096 blocks=12799, version=2
loa
                    sectsz=512 sunit=0 blks, lazy-count=1
                        extsz=4096 blocks=0, rtextents=0
realtime =none
data blocks changed from 26213888 to 39321339
```

Step 7 Run the following command to view the new capacity of the /dev/vdb1 partition:

df -TH

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# df -TH
          Type Size Used Avail Use% Mounted on
Filesystem
devtmpfs
           devtmpfs 509M 0 509M 0% /dev
         tmpfs 520M 0 520M 0% /dev/shm
tmpfs
                 520M 7.1M 513M 2% /run
tmpfs
         tmpfs
                520M 0 520M 0% /sys/fs/cgroup
tmpfs
         tmpfs
/dev/vda1
                 43G 2.3G 38G 6% /
          ext4
                 104M 0 104M 0% /run/user/0
tmpfs
         tmpfs
/dev/vdb1 ext4 159G 63M 151G 1% /mnt/sdc
```


If the server is restarted, the mounting will become invalid. You can set automatic mounting for partitions at system start by modifying the /etc/fstab file. For details, see Setting Automatic Mounting at System Start.

----End

Creating a New MBR Partition

Originally, data disk /dev/vdb has 100 GB and one partition (/dev/vdb1), and then 50 GB is added to the disk. The following procedure shows you how to create a new MBR partition /dev/vdb2 with this 50 GB.

Step 1 Run the following command to view the disk partition information:

fdisk -l

```
[root@ecs-test-0001 ~]# fdisk -l
Disk /dev/vda: 42.9 GB, 42949672960 bytes, 83886080 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000bcb4e
```

```
Device Boot Start End Blocks Id System

/dev/vda1 * 2048 83886079 41942016 83 Linux

Disk /dev/vdb: 161.1 GB, 161061273600 bytes, 314572800 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes

I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dos

Disk identifier: 0x38717fc1

Device Boot Start End Blocks Id System
```

Step 2 Run the following command to enter fdisk:

fdisk Disk

/dev/vdb1

In this example, run the following command:

fdisk /dev/vdb

Information similar to the following is displayed:

[root@ecs-test-0001 ~]# fdisk /dev/vdb Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them. Be careful before using the write command.

2048 209715199 104856576 83 Linux

Command (m for help):

Step 3 Enter **n** and press **Enter** to create a new partition.

Information similar to the following is displayed:

```
Command (m for help): n
Partition type:
   p primary (1 primary, 0 extended, 3 free)
   e extended
Select (default p):
```

There are two types of disk partitions:

- Choosing **p** creates a primary partition.
- Choosing e creates an extended partition.

◯ NOTE

If the MBR partition style is used, a maximum of 4 primary partitions, or 3 primary partitions and 1 extended partition can be created. The extended partition cannot be used directly and must be divided into logical partitions before use.

Disk partitions created using GPT are not categorized.

Step 4 In this example, a primary partition is created. Therefore, enter **p** and press **Enter** to create a primary partition.

Information similar to the following is displayed:

```
Select (default p): p
Partition number (2-4, default 2):
```

Partition number indicates the serial number of the primary partition. Because partition number 1 has been used, the value ranges from **2** to **4**.

Step 5 Enter the serial number of the primary partition and press Enter. Partition number2 is used in this example. Therefore, enter 2 and press Enter.

Partition number (2-4, default 2): 2 First sector (209715200-314572799, default 209715200):

First sector indicates the start sector. The value ranges from **209715200** to **314572799**, and the default value is **209715200**.

Step 6 Enter the new partition's start sector and press **Enter**. In this example, the default start sector is used.

The system displays the start and end sectors of the partition's available space. You can customize the value within this range or use the default value. The start sector must be smaller than the partition's end sector.

Information similar to the following is displayed:

First sector (209715200-314572799, default 209715200):
Using default value 209715200
Last sector, +sectors or +size{K,M,G} (209715200-314572799, default 314572799):

Last sector indicates the end sector. The value ranges from **209715200** to **314572799**, and the default value is **314572799**.

Step 7 Enter the new partition's end sector and press **Enter**. In this example, the default end sector is used.

The system displays the start and end sectors of the partition's available space. You can customize the value within this range or use the default value. The start sector must be smaller than the partition's end sector.

Information similar to the following is displayed:

Last sector, +sectors or +size $\{K,M,G\}$ (209715200-314572799, default 314572799): Using default value 314572799 Partition 2 of type Linux and of size 50 GiB is set

. area or 5, pe _...ar and or 5, 20 or or

Step 8 Enter **p** and press **Enter** to view the new partition.

Information similar to the following is displayed:

Command (m for help): p

Command (m for help):

Disk /dev/vdb: 161.1 GB, 161061273600 bytes, 314572800 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dos Disk identifier: 0x38717fc1

Device Boot Start End Blocks Id System /dev/vdb1 2048 209715199 104856576 83 Linux /dev/vdb2 209715200 314572799 52428800 83 Linux

Command (m for help):

Step 9 Enter **w** and press **Enter** to write the changes to the partition table.

Information similar to the following is displayed:

Command (m for help): w

The partition table has been altered!

Calling ioctl() to re-read partition table.

WARNING: Re-reading the partition table failed with error 16: Device or resource busy. The kernel still uses the old table. The new table will be used at the part reheat or after you run partnersho(2) or knowledge.

the next reboot or after you run partprobe(8) or kpartx(8)

Syncing disks.

In case that you want to discard the changes made before, you can exit fdisk by entering ${f q}$.

Step 10 Run the following command to synchronize the new partition table to the OS:

partprobe

Step 11 Run the following command to set the file system format for the new partition:

mkfs -t File system Disk partition

• Sample command of the ext* file system:

mkfs -t ext4 /dev/vdb2

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# mkfs -t ext4 /dev/vdb2
mke2fs 1.42.9 (28-Dec-2013)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
3276800 inodes, 13107200 blocks
655360 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=2162163712
400 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
Superblock backups stored on blocks:
     32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208,
     4096000, 7962624, 11239424
Allocating group tables: done
Writing inode tables: done
Creating journal (32768 blocks): done
Writing superblocks and filesystem accounting information: done
```

• Sample command of the xfs file system:

mkfs -t xfs /dev/vdb2

Information similar to the following is displayed:

The formatting takes a while, and you need to observe the system running status. Once **done** is displayed in the command output, the formatting is complete.

Step 12 (Optional) Run the following command to create a mount point:

Perform this step if you want to mount the partition on a new mount point.

mkdir Mount point

In this example, run the following command to create the /mnt/test mount point:

mkdir /mnt/test

Step 13 Run the following command to mount the new partition:

mount Disk partition Mount point

In this example, run the following command to mount the new partition /dev/vdb2 on /mnt/test:

mount /dev/vdb2 /mnt/test

If the new partition is mounted on a directory that is not empty, the subdirectories and files in the directory will be hidden. Therefore, you are advised to mount the new partition on an empty directory or a new directory. If the new partition must be mounted on a directory that is not empty, move the subdirectories and files in this directory to another directory temporarily. After the partition is successfully mounted, move the subdirectories and files back.

Step 14 Run the following command to view the mount result:

df ₋TH

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# df -TH
                  Size Used Avail Use% Mounted on
Filesystem
           Type
/dev/vda1
           ext4
                  43G 1.9G 39G 5%/
           devtmpfs 2.0G 0 2.0G 0% /dev
devtmpfs
          tmpfs 2.0G 0 2.0G 0% /dev/shm
tmpfs
tmpfs
          tmpfs
                 2.0G 9.1M 2.0G 1% /run
tmpfs
                 2.0G 0 2.0G 0% /sys/fs/cgroup
          tmpfs
                 398M 0 398M 0% /run/user/0
          tmpfs
tmpfs
/dev/vdb1
           ext4
                  106G 63M 101G 1% /mnt/sdc
/dev/vdb2
           ext4
                  53G 55M 50G 1% /mnt/test
```

□ NOTE

If the server is restarted, the mounting will become invalid. You can set automatic mounting for partitions at system start by modifying the /etc/fstab file. For details, see Setting Automatic Mounting at System Start.

----End

Creating a New GPT Partition

Originally, data disk /dev/vdb has 100 GB and one partition (/dev/vdb1), and then 50 GB is added to the disk. The following procedure shows you how to create a new GPT partition /dev/vdb2 with this 50 GB.

Step 1 Run the following command to view the disk partition information:

lsblk

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# lsblk
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda 253:0 0 40G 0 disk
__vda1 253:1 0 40G 0 part /
vdb 253:16 0 150G 0 disk
__vdb1 253:17 0 100G 0 part /mnt/sdc
```

Step 2 Run the following command to enter parted:

parted Disk

In this example, run the following command:

parted /dev/vdb

Information similar to the following is displayed:

[root@ecs-test-0001 ~]# parted /dev/vdb GNU Parted 3.1 Using /dev/vdb Welcome to GNU Parted! Type 'help' to view a list of commands. (parted)

- **Step 3** Enter **unit s** and press **Enter** to set the measurement unit of the disk to sector.
- **Step 4** Enter **p** and press **Enter** to view the disk partition information.

Information similar to the following is displayed:

(parted) unit s (parted) p

Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that another operating system believes the

disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?

Fix/Ignore/Cancel? Fix

Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all of the space (an extra 104857600

blocks) or continue with the current setting?

Fix/Ignore? Fix

Model: Virtio Block Device (virtblk)

Disk /dev/vdb: 314572800s

Sector size (logical/physical): 512B/512B

Partition Table: gpt

Disk Flags:

Number Start End Size File system Name Flags 1 2048s 209713151s 209711104s ext4 test

(parted)

In the command output, take note of the partition's end sector. In this example, the end sector of the /dev/vdb1 partition is 209713151s.

• If the following error information is displayed, enter **Fix**.

Error: The backup GPT table is not at the end of the disk, as it should be. This might mean that another operating system believes the disk is smaller. Fix, by moving the backup to the end (and removing the old backup)?

The GPT partition table information is stored at the start of the disk. To reduce the risk of damage, a backup of the information is saved at the end of the disk. When you expand the disk capacity, the end of the disk changes accordingly. In this case, enter **Fix** to move the backup file of the information to new disk end.

• If the following warning information is displayed, enter **Fix**.

Warning: Not all of the space available to /dev/vdb appears to be used, you can fix the GPT to use all of the space (an extra 104857600

blocks) or continue with the current setting?

Fix/Ignore? Fix

Enter **Fix** as prompted. The system automatically sets the GPT partition style for the additional space.

Step 5 Run the following command and press **Enter**:

mkpart Partition name Start sector End sector

In this example, run the following command:

mkpart data 209713152s 100%

In this example, the additional space is used to create a new partition. In **Step 4**, the end sector of partition **dev/vdb1** is **209713151s**. Therefore, the start sector of the new partition **dev/vdb2** is set to **209713152s** and the end sector **100%**. This start and end sectors are for reference only. You can plan the number of partitions and partition size based on service requirements.

Information similar to the following is displayed:

(parted) mkpart data 209713152s 100% (parted)

The maximum sector can be obtained in either of the following ways:

- Query the disk's maximum end sector. For details, see Step 2 to Step 4.
- Enter -1s or 100%, and the value displayed is the maximum end sector.

Step 6 Enter **p** and press **Enter** to view the new partition.

Information similar to the following is displayed:

```
(parted) p
Model: Virtio Block Device (virtblk)
Disk /dev/vdb: 314572800s
Sector size (logical/physical): 512B/512B
Partition Table: gpt
Disk Flags:
Number Start
                 End
                          Size
                                   File system Name Flags
              209713151s 209711104s ext4
     2048s
                                                 test
     209713152s 314570751s 104857600s
                                                   data
(parted)
```

Step 7 Enter **q** and press **Enter** to exit parted.

Information similar to the following is displayed:

```
(parted) q
Information: You may need to update /etc/fstab.
```

You can set automatic disk mounting by updating the /etc/fstab file. Before updating the file, set the file system format for the partition and mount the partition on the mount point.

Step 8 Run the following command to set the file system format for the new partition:

mkfs -t File system Disk partition

• Sample command of the ext* file system:

mkfs -t ext4 /dev/vdb2

```
[root@ecs-test-0001 ~]# mkfs -t ext4 /dev/vdb2 mke2fs 1.42.9 (28-Dec-2013)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
3276800 inodes, 13107200 blocks
655360 blocks (5.00%) reserved for the super user
First data block=0
Maximum filesystem blocks=2162163712
400 block groups
32768 blocks per group, 32768 fragments per group
8192 inodes per group
```

```
Superblock backups stored on blocks:
32768, 98304, 163840, 229376, 294912, 819200, 884736, 1605632, 2654208,
4096000, 7962624, 11239424

Allocating group tables: done
Writing inode tables: done
Creating journal (32768 blocks): done
Writing superblocks and filesystem accounting information: done
```

• Sample command of the xfs file system:

mkfs -t xfs /dev/vdb2

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# mkfs -t xfs /dev/vdb2
meta-data=/dev/vdb2
                                     agcount=4, agsize=3276800 blks
                           isize=512
                   sectsz=512 attr=2, projid32bit=1
                    crc=1
                            finobt=0, sparse=0
                    bsize=4096 blocks=13107200, imaxpct=25
data =
                    sunit=0 swidth=0 blks
naming =version2
                        bsize=4096 ascii-ci=0 ftype=1
                       bsize=4096 blocks=6400, version=2
     =internal log
                    sectsz=512 sunit=0 blks, lazy-count=1
realtime =none
                        extsz=4096 blocks=0, rtextents=0
```

The formatting takes a while, and you need to observe the system running status. Once **done** is displayed in the command output, the formatting is complete.

Step 9 (Optional) Run the following command to create a mount point:

Perform this step if you want to mount the partition on a new mount point.

mkdir Mount point

In this example, run the following command to create the /mnt/test mount point:

mkdir /mnt/test

Step 10 Run the following command to mount the new partition:

```
mount Disk partition Mount point
```

In this example, run the following command to mount the new partition /dev/vdb2 on /mnt/test:

mount /dev/vdb2 /mnt/test

■ NOTE

If the new partition is mounted on a directory that is not empty, the subdirectories and files in the directory will be hidden. Therefore, you are advised to mount the new partition on an empty directory or a new directory. If the new partition must be mounted on a directory that is not empty, move the subdirectories and files in this directory to another directory temporarily. After the partition is successfully mounted, move the subdirectories and files back.

Step 11 Run the following command to view the mount result:

df -TH

```
[root@ecs-test-0001 ~]# df -TH
Filesystem Type Size Used Avail Use% Mounted on
/dev/vda1 ext4 43G 1.9G 39G 5% /
devtmpfs devtmpfs 2.0G 0 2.0G 0% /dev
tmpfs tmpfs 2.0G 0 2.0G 0% /dev/shm
tmpfs tmpfs 2.0G 9.1M 2.0G 1% /run
```

tmpfs	tmpfs	2.0G	0 2.0G 0% /sys/fs/cgroup
tmpfs	tmpfs	398M	0 398M 0% /run/user/0
/dev/vdb1	ext4	106G	63M 101G 1% /mnt/sdc
/dev/vdb2	ext4	53G 5	55M 50G 1% /mnt/test

◯ NOTE

If the server is restarted, the mounting will become invalid. You can set automatic mounting for partitions at system start by modifying the /etc/fstab file. For details, see Setting Automatic Mounting at System Start.

----End

Setting Automatic Mounting at System Start

To automatically mount disk partitions at system start, do not specify partitions, for example /dev/vdb1, in /etc/fstab because the sequence of cloud devices, and therefore their names may change during the server stop and start. You are advised to use the universally unique identifier (UUID) in /etc/fstab to set automatic mounting at system start.

UUID is the unique character string for disk partitions in a Linux system.

Step 1 Run the following command to query the partition UUID:

blkid Disk partition

In this example, run the following command to query the UUID of the /dev/vdb1 partition:

blkid /dev/vdb1

Information similar to the following is displayed:

```
[root@ecs-test-0001 ~]# blkid /dev/vdb1
/dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4"
```

The UUID of the /dev/vdb1 partition is displayed.

Step 2 Run the following command to open the **fstab** file using the vi editor:

vi /etc/fstab

- **Step 3** Press **i** to enter the editing mode.
- **Step 4** Move the cursor to the end of the file and press **Enter**. Then, add the following information:

```
UUID=0b3040e2-1367-4abb-841d-ddb0b92693df /mnt/sdc ext4 defaults 0 2
```

The preceding content is used for reference only. Add the information that is used in the environment. The parameters are described as follows:

- The first column indicates the partition UUID obtained in **Step 1**.
- The second column indicates the directory on which the partition is mounted. You can query the mount point using the **df-TH** command.
- The third column indicates the file system format of the partition. You can query the file system format using the **df** -**TH** command.
- The fourth column indicates the partition mount option. Normally, this parameter is set to defaults.

- The fifth column indicates the Linux dump backup option.
 - **0**: not use Linux dump backup. Normally, dump backup is not used, and you can set this parameter to **0**.
 - 1: use Linux dump backup.
- The sixth column indicates the fsck option, that is, whether to use fsck to check the attached disk during startup.
 - 0: not use fsck.
 - If the mount point is the root partition (/), this parameter must be set to 1

When this parameter is set to **1** for the root partition, this parameter for other partitions must start with **2** so that the system checks the partitions in the ascending order of the values.

Step 5 Press **Esc**, enter :wq, and press **Enter**.

The system saves the configurations and exits the vi editor.

Step 6 Perform the following operations to verify the automatic mounting function:

1. Run the following command to unmount the partition:

umount Disk partition

In this example, run the following command:

umount /dev/vdb1

- 2. Run the following command to reload all the content in the /etc/fstab file: mount -a
- 3. Run the following command to query the file system mounting information:

mount | grep Mount point

In this example, run the following command:

mount | grep /mnt/sdc

If information similar to the following is displayed, the automatic mounting function takes effect:

root@ecs-test-0001 ~]# mount | grep /mnt/sdc /dev/vdb1 on /mnt/sdc type ext4 (rw,relatime,data=ordered)

----End

2 Detaching an EVS Disk

2.1 Detaching a System Disk

Scenarios

A system disk can only be detached offline, that is, its server must be in the **Stopped** state before the system disk is detached. Therefore, you need to first stop the server and then detach the system disk.

For the system disk attached to a server, the disk function is displayed as **System disk**, and the disk status is displayed as **In-use** in the disk list. After a system disk is detached from the server, the disk function changes to **Bootable disk**, and the status changes to **Available**.

□ NOTE

Bootable disks are the system disks detached from servers. A bootable disk can be reattached to a server and be used as a system disk or data disk depending on the device name selected.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Computing**, click **Elastic Cloud Server**.

The Elastic Cloud Server page is displayed.

Step 3 In the server list, locate the row that contains the server whose system disk is to be detached, click **More** in the **Operation** column, and choose **Stop**.

When the server status changes to **Stopped**, the server has been stopped.

Step 4 Click the name of this server.

The server details page is displayed.

- **Step 5** Click the **Disks** tab to view the system disk attached to the server.
- **Step 6** Locate the row that contains the system disk and click **Detach**.

The **Detach Disk** dialog box is displayed.

Step 7 Click **Yes** to detach the disk.

After the operation had succeeded, the detached system disk is no longer displayed under the **Disks** tab.

- **Step 8** (Optional) Bootable disks are the system disks detached from servers. A bootable disk can be re-attached to a server and be used as a system disk or data disk depending on the device name selected.
 - To re-attach and use it as a system disk, see 3.1 Attaching an Existing System Disk.
 - To re-attach and use it as a data disk, see 3.2 Attaching an Existing Non-Shared Disk.

----End

Related Operations

For more detachment FAQs, see **Disk Detachment FAQs**.

2.2 Detaching a Data Disk

Scenarios

Data disks can be detached online or offline, which means that the server containing the to-be-detached data disk can either be in the **Running** or **Stopped** state.

ECS

Detach an EVS disk online. For details, see **Detaching an EVS Disk from a Running ECS**.

BMS

Currently, SCSI disks can be attached to BMSs and used as data disks. You can detach a data disk either from a running or stopped BMS.

For a data disk attached to a server, the disk function is displayed as **Data disk**, and the disk status is displayed as **In-use** in the disk list. After the data disk has been detached from the server, the disk function remains unchanged, the disk status changes to **Available** for a non-shared data disk, and the disk status changes to **Available** for a shared data disk after it is detached from all its servers.

Precautions

Disk data may be lost after you detach a disk. For more information, see **Will**Data in the EVS Disk Be Lost After the EVS Disk Is Detached?

Prerequisites

 Before detaching an EVS disk from a running Windows ECS, make sure that VMTools have been installed on the ECS and that the tools are running properly.

- Before detaching an EVS disk from a running Windows ECS, ensure that no program is reading data from or writing data to the disk. Otherwise, data will be lost.
- Before detaching an EVS disk from a running Linux ECS, you must log in to the ECS and run the **umount** command to cancel the association between the disk and the file system. In addition, ensure that no program is reading data from or writing data to the disk. Otherwise, detaching the disk will fail.

Detaching a Non-shared Disk

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

- **Step 3** Determine whether to view the server information before detaching the disk.
 - If you need to view the server information, perform the following procedure:
 - a. In the disk list, click the name of the to-be-detached disk.The disk details page is displayed.
 - b. Click the **Servers** tab to view the server where the target disk has been attached.
 - c. Click to select the server and click **Detach Disk**.

 The **Detach Disk** dialog box is displayed.
 - d. Click Yes to detach the disk.
 - If you do not need to view the server information, perform the following procedure:
 - a. In the disk list, locate the row that contains the target disk and choose **More** > **Detach** in the **Operation** column.

The **Detach Disk** dialog box is displayed.

b. Click Yes to detach the disk.

The disk list is displayed. The disk status is **Detaching**, indicating that the disk is being detached from the server.

When the status changes to **Available**, the disk is successfully detached.

----End

3 Attaching an Existing Disk

3.1 Attaching an Existing System Disk

Scenarios

This topic describes how to attach an existing system disk.

Currently, system disks can only be attached offline, which means that the server must be in the **Stopped** state.

You can view the disk function in the disk list. A disk can be attached to a server and used as the system disk only when its function is **Bootable disk** and its status is **Available**.

Ⅲ NOTE

- Bootable disks are the system disks detached from servers. A bootable disk can be reattached to a server and be used as a system disk or data disk depending on the device name selected.
- A yearly/monthly disk purchased with a yearly/monthly server cannot be attached to other servers.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

Step 3 Locate the target disk in the list and click **Attach**.

A disk can be attached to a server and used as the system disk only when its function is **Bootable disk** and its status is **Available**.

Step 4 Select a server and then select a device name from the drop-down list. Ensure that the disk and server are in the same AZ and that the server is in the **Stopped** state.

One device name can be attached with one disk only. For the mapping between device names displayed on the management console and those on the server, see

What Is the Mapping Between Device Names and Disks? in the *Elastic Cloud Server User Guide*.

Step 5 Click OK to return to the disk list page. The status of the disk is Attaching, indicating that the disk is being attached to the server. When the function of the disk changes from Bootable disk to System disk and the disk status changes to In-use, the disk is successfully attached.

----End

Related Operations

If your disk cannot be attached to a server, see Why My EVS Disk Cannot Be Attached to a Server?

For more attachment FAQs, see **Disk Attachment FAQs**.

3.2 Attaching an Existing Non-Shared Disk

Scenarios

This topic describes how to attach an existing non-shared disk to a server and use it as data disk. A non-shared disk can be attached to one server only.

You can view the disk information in the disk list. A disk can be attached to a server and used as the data disk when all of the following conditions are met:

- Disk Sharing: Disabled
- Function: Bootable disk or Data disk
- Status: Available

□ NOTE

- Bootable disks are the system disks detached from servers. A bootable disk can be reattached to a server and be used as a system disk or data disk depending on the device name selected.
- A yearly/monthly disk purchased with a yearly/monthly server cannot be attached to other servers.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Storage**, click **Elastic Volume Service**.

The disk list page is displayed.

Step 3 Locate the target disk in the list and click **Attach**.

A disk can be attached to a server and used as a data disk only when its function is **Bootable disk** or **Data disk** and its status is **Available**.

Step 4 Select a server and then select a device name from the drop-down list. Ensure that the disk and server are in the same AZ.

One device name can be attached with one disk only. For the mapping between device names displayed on the management console and those on the server, see

What Is the Mapping Between Device Names and Disks? in the *Elastic Cloud Server User Guide*.

Step 5 Click **OK** to return to the disk list page. The status of the disk is **Attaching**, indicating that the disk is being attached to the server. When the disk status changes to **In-use**, the disk is successfully attached.

----End

Related Operations

If your disk cannot be attached to a server, see Why My EVS Disk Cannot Be Attached to a Server?

For more attachment FAQs, see Disk Attachment FAQs.

3.3 Attaching an Existing Shared Disk

Scenarios

This topic describes how to attach an existing shared disk to a server and use it as data disk.

You can view the disk information in the disk list. A shared disk can be attached to servers and used as data disks when all of the following conditions are met:

Disk Sharing: Enabled

• Function: Data disk

Status: In-use or Available

Constraints

- A shared disk can be attached to a maximum of 16 servers. These servers and the shared disk must be in the same AZ within a region.
- If a shared disk is in the **In-use** state, ensure that the maximum number of servers that the disk can be attached to has not been reached.
- All the servers of a shared disk must run either Windows or Linux no matter the disk is attached to them in a batch or individually.
 - For example, if you attach a shared disk to multiple Windows servers in a batch and then detach it from all its servers, the disk cannot be attached to Linux servers later. This is because Windows and Linux support different file systems and cannot identify the original file system on the disk. Improper operations may damage the original file system.
- A shared disk can only be used as a data disk. It cannot be used as a system disk.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

- **Step 3** Locate the target disk in the list and click **Attach**.
 - Shared disks support batch attachment so that you can attach a shared disk to multiple servers at a time. The left area in the **Attach Disk** dialog box shows the server list. After you select the target servers, the selected servers will be displayed in the right area.
 - A shared disk can be attached to servers only when the disk status is
 Available or In-use.
- **Step 4** Select the target servers and then select a device name from the drop-down list for each server you selected. Ensure that the disk and servers are in the same AZ.
 - One device name can be attached with one disk only. If a device name has been used, it will no longer be displayed in the drop-down list and cannot be selected.
- **Step 5** Click **OK** to return to the disk list page. The status of the disk is **Attaching**, indicating that the disk is being attached to the servers. When the disk status changes to **In-use**, the disk is successfully attached.

NOTICE

If you simply attach a shared disk to multiple servers, files cannot be shared between the servers as shared disks do not have the cluster capability. Therefore, build a shared file system or deploy a cluster management system to share files between servers.

----End

Related Operations

If your disk cannot be attached to a server, see Why My EVS Disk Cannot Be Attached to a Server?

For more attachment FAQs, see Disk Attachment FAQs.

4 Deleting an EVS Disk

Scenarios

If an EVS disk is no longer used, you can release the virtual resources by deleting the disk from the system.

After a disk is deleted, you are no longer charged for it. The storage system immediately destroys the metadata so that data can no longer be accessed. In addition, the physical storage space of the disk is recycled and will be re-assigned only after being cleared. Before data is written to a new disk, the system returns only zero for all read requests.

Pay-per-use disk:

Can be deleted only when all the following conditions are met:

- The disk status is Available, Error, Expansion failed, Restoration failed, or Rollback failed.
- The disk is not added to any replication pair in SDRS. If the disk has been added to a replication pair, delete the replication pair and then delete the disk.
- The disk is not locked by any service.
- Yearly/Monthly disk:

Cannot be deleted, but you can unsubscribe from the disk if needed. For details about the unsubscription rules and operation methods, see **Billing Center User Guide**.

NOTICE

- When you delete a disk, all the disk data including the snapshots created for this disk will be deleted. Exercise caution when performing this operation.
- A deleted disk cannot be recovered.

Procedure

Step 1 Log in to the management console.

Ste	p 2	Under Storage , click Elastic Volume Service .		
		The disk list page is displayed.		
Ste	р 3	In the disk list, locate the row that contains the target disk, click More in the Operation column, and choose Delete .		
Ste	p 4	(Optional) If multiple disks are to be deleted, select and click Delete in the upper area of the list.		
Ste	p 5	In the displayed dialog box, confirm the information and click Yes.		
		End		

Related Operations

For more deletion FAQs, see **Disk Deletion FAQs**.

5 Viewing Disk Details

Scenarios

This topic describes how to view disk details, including the disk status and specifications. You can view disk details:

- From the EVS Console
- From the Server Console

See A.1 EVS Disk Status to learn the description of each disk status.


From the EVS Console

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

Step 3 In the disk list, view disk information including the disk status, type, size, function, and device type.

You can filter disks by project, status, disk name, or tag.



Step 4 (Optional) Export disk information.

Click in the upper right corner of the list to export disk information.


----End

From the Server Console

- **Step 1** Log in to the management console.
- Step 2 Under Computing, click Elastic Cloud Server.
 - The **Elastic Cloud Server** page is displayed.
- **Step 3** In the server list, locate the corresponding server by server name and click the name.
 - The server details page is displayed.
- **Step 4** On the **Disks** tab, click in front of the row containing the target disk. In the unfolded area, click the disk ID.

The disk details page is displayed, and you can view the disk details.

Figure 5-1 Disk details page



----End

6 Managing an Encrypted EVS Disk

Relationships Among Encrypted Disks, Backups, Images, and Snapshots

The encryption function can be used to encrypt system disks, data disks, images, and snapshots. The details are as follows:

- System disk encryption relates to the image that is used to create the server.
 - If an encrypted image is used to create the server, encryption is enabled for the system disk by default, and the system disk and image share the same encryption method. For details, see Managing Private Images > Encrypting Images in the Image Management Service User Guide.
- When creating an empty disk, you can determine whether to encrypt the disk or not. The disk encryption attribute cannot be changed after the disk has been created.
- If a disk is created from a snapshot, the encryption attribute of the disk will be the same as that of the snapshot's source disk.
- If a disk is created from a backup, the encryption attribute of the disk will be the same as that of the backup's source disk.
- If a disk is created from an image, the encryption attribute of the disk will be the same as that of the image's source disk.
- If a backup is created for a disk, the encryption attribute of the backup is the same as that of the disk.
- If a snapshot is created for a disk, the encryption attribute of the snapshot is the same as that of the disk.

Creating an Encrypted EVS Disk

Before you use the disk encryption function, KMS access rights need to be granted to EVS. If you have the Security Administrator rights, grant the KMS access rights to EVS directly. If you do not have this permission, contact a user with the security administrator rights to grant KMS access rights to EVS, then repeat the preceding operations.

Detaching an Encrypted EVS Disk

Before you detach an EVS disk encrypted by a CMK, check whether the CMK is disabled or scheduled for deletion. If the CMK is unavailable, the disk can still be

used, but normal read/write operations are not guaranteed permanently. If the disk is detached and then re-attached, re-attaching this disk will fail. In this case, do not detach the disk and restore the CMK status first.

The restoration method varies depending on the current CMK status. For details, see **EVS Disk Encryption**.

If the CMK is available, the disk can be detached and re-attached, and data on the disk will not be lost.

For details about how to detach an encrypted disk, see **2.2 Detaching a Data Disk**.

Managing a Shared EVS Disk

How to Use Shared VBD and SCSI Disks?

You can create shared VBD disks or shared SCSI disks. It is recommended that you attach the shared disk to the ECSs in the same ECS group to improve service reliability.

- Shared VBD EVS disks: The device type of a newly created shared EVS disk is VBD by default. Such disks can be used as virtual block storage devices, but do not support SCSI reservations. If SCSI reservations are required for your applications, create shared SCSI EVS disks.
- Shared SCSI EVS disks: These EVS disks support SCSI reservations.

NOTICE

- To improve data security, you are advised to use SCSI reservations together
 with the anti-affinity policy of an ECS group. That said, ensure that shared
 SCSI EVS disks are only attached to ECSs in the same anti-affinity ECS
 group.
- If an ECS does not belong to any anti-affinity ECS group, you are advised not to attach shared SCSI EVS disks to this ECS. Otherwise, SCSI reservations may not work properly, which may put your data at risk.

Concepts of the anti-affinity ECS group and SCSI reservations:

- The anti-affinity policy of an ECS group allows ECSs to be created on different physical servers to improve service reliability.
 For details about ECS groups, see Managing ECS Groups.
- The SCSI reservation mechanism uses a SCSI reservation command to perform SCSI reservation operations. If an ECS sends such a command to an EVS disk, the disk is displayed as locked to other ECSs, preventing the data damage that may be caused by simultaneous read/write operations to the disk from multiple ECSs.
- ECS groups and SCSI reservations have the following relationship: A SCSI reservation on a single EVS disk cannot differentiate multiple ECSs on the same physical host. For that reason, if multiple ECSs that use the same shared EVS disk are running on the same physical host, SCSI reservations

will not work properly. Therefore, you are advised to use SCSI reservations only on ECSs that are in the same ECS group, thus having a working antiaffinity policy.

Attaching a Shared EVS Disk

A common EVS disk can only be attached to one server, whereas a shared EVS disk can be attached to up to 16 servers.

For details, see **Attaching a Shared Disk**.

Deleting a Shared EVS Disk

Because a shared EVS disk can be attached to multiple servers, ensure that the shared EVS disk is detached from all the servers before deletion.

For details about how to delete a shared EVS disk, see 4 Deleting an EVS Disk.

Expanding a Shared EVS Disk

Shared EVS disks must be expanded when they are in the **Available** state. For details, see **1.3 Expanding Capacity for an Available EVS Disk**.

Related Operations

For more disk sharing FAQs, see **Shared Disk FAQs**.

8 Managing EVS Backup

Scenarios

EVS disk backups are created using the CBR service.

This topic describes how to configure a backup policy for disks. With backup policies configured, data on EVS disks can be periodically backed up to improve data security.

◯ NOTE

Create the backups only when EVS disks are in the Available or In-use state.

Purchasing a Disk Backup Vault and Configuring the Backup Policy

- **Step 1** Log in to the CBR console.
 - 1. Log in to the management console.
 - 2. Choose Storage > Cloud Backup and Recovery > Cloud Disk Backup.
- Step 2 In the upper right corner, click Buy Disk Backup Vault.
- **Step 3** Select a billing mode.
 - Select the yearly/monthly mode if you have a good idea of what resources you will need during the billing period. Fees need to be paid in advance, but services will be less expensive.
 - Pay-per-use is a postpaid billing mode. Select this mode, and you will be billed based on the usage of resources. You may purchase or delete resources at any time, and fees will be deducted from the account balance.
- **Step 4** (Optional) Select the disks you want to back up in the disk list. After the disks are selected, they will appear in the right area.

Selected Disks (2) ▼ All statuses ▼ Name ▼ Q QC All projects Name Status ECS/BMS Capacity (GB) Associated Status FCS/BMS Capacity (GB) Operation Name ecs-IsIs-volume... In-use 10 No ecs-IsIs ecs-IsIs In-use volume-disk Available 10 No ecs-3cfe-volum... Available

Figure 8-1 Selecting disks

□ NOTE

- Only the Available or In-use disks can be selected.
- You can associate desired disks with the vault you created later if you skip this step.
- **Step 5** Specify the vault capacity. This capacity indicates the total size of the disks that you want to associate with this vault. Therefore, specify a vault capacity that is greater than or equal to the total size of the disks you want to back up. The value ranges from the total size of the disks to 10,485,760 in the unit of GB.
- **Step 6** Determine whether to configure auto backup.
 - If you select Configure, you must then select an existing backup policy or create a new one. After the vault is created, the system associates the vault with this backup policy, and all disks associated with this vault will be automatically backed up according to this policy.
 - If you select **Skip**, disks associated with this vault are not automatically backed up.
- **Step 7** If you have subscribed to the Enterprise Project Management Service (EPS), add the vault to an existing enterprise project.

EPS provides a unified method to manage cloud resources by project, allowing you to manage resources, users, and user groups in your projects. The default project is **default**.

Step 8 (Optional) Add tags for the vault.

A tag consists of a key-value pair. Tags are used to identify, classify, and search for vaults. Vault tags are used to filter and manage vaults only. You can add up to 10 tags for a vault.

Table 8-1 describes the tag parameters.

Table 8-1 Parameter description

Para mete r	Description	Example Value
Key	A tag key of a vault must be unique. You can customize the key or select the key of an existing tag created in TMS.	Key_0001
	A tag key must comply with the following rules:	
	Contains 1 to 36 Unicode characters.	
	 Cannot be empty, cannot start or end with spaces, or contain non-printable ASCII (0-31) characters or the following special characters: =*<> / 	
Value	A tag value can be repetitive or left blank.	Value_0001
	A tag value must comply with the following rules:	
	Contains 0 to 43 Unicode characters.	
	• Can be an empty string, cannot start or end with spaces, or contain non-printable ASCII (0-31) characters or the following special characters: =*<> /	

Step 9 Specify the vault name.

A name is a string of 1 to 64 characters consisting of digits, letters, underscores (_), and hyphens (-), for example, **vault-612c**.

□ NOTE

You can use the default name, which is in the format of **vault_**xxxx.

Step 10 Specify the subscription duration if you select **Yearly/Monthly** for **Billing Mode**. The validity period ranges from 1 month to 3 years.

Determine whether to enable auto renewal. If **Auto Renewal** is selected, the subscription is renewed according to the following rules:

- Monthly subscription: Your order will be renewed each month.
- Yearly subscription: Your order will be renewed each year.
- **Step 11** Click **Next**. Confirm the purchase details and click **Submit**.
- **Step 12** Pay for the order as prompted.
- **Step 13** Go back to the disk backup page. The vault you created is displayed in the list.

You can associate disks to the new vault or create backups for disks. For details, see **Vault Management**.

9 Managing Snapshots (OBT)

9.1 Snapshot Overview (OBT)

What Is EVS Snapshot

EVS allows you to create snapshots for disks on the management console or by making API calls. An EVS snapshot is a complete copy or image of the disk data at a specific time point. As a major disaster recovery (DR) approach, you can use a snapshot to completely restore the data to the time point when the snapshot was created.

EVS snapshots are sometimes referred to as snapshots in this document.

You can create snapshots to rapidly save the disk data at specified time points. In addition, you can use snapshots to create new disks so that the created disks will contain the snapshot data in the beginning.

Application Scenarios

The snapshot function helps address your following needs:

Routine data backup

You can create snapshots for disks on a timely basis and use snapshots to recover your data in case that data loss or data inconsistency occurred due to misoperations, viruses, or attacks.

• Rapid data restoration

You can create a snapshot or multiple snapshots before an application software upgrade or a service data migration. If an exception occurs during the upgrade or migration, service data can be rapidly restored to the time point when the snapshot was created.

For example, a fault occurred on system disk A of server A, and therefore server A cannot be started. Because system disk A is already faulty, the data on system disk A cannot be restored by rolling back snapshots. However, you can create disk B using an existing snapshot of system disk A and attach disk B to a properly running server, for example server B. In this case, server B can read the data of system disk A from disk B.

□ NOTE

Currently, when rolling back data from snapshots, the snapshot data can be rolled back only to its source EVS disk, and a rollback to another EVS disk is not possible.

Multi-service quick deployment

You can use a snapshot to create multiple disks containing the same initial data, and these disks can be used as data resources for various services, for example data mining, report query, and development and testing. This method protects the initial data and creates disks rapidly, meeting the diversified service data requirements.

Operation Overview

You can create snapshots according to **9.2 Creating a Snapshot (OBT)** to rapidly save the disk data at specified points in time.

If data lost occurs, you may choose to roll back the disk data to the snapshot creation time based on **9.5 Rolling Back Data from a Snapshot (OBT)**. In addition, you may create a new disk from the snapshot so that the disk will contain the snapshot data in the beginning. For details, see **9.6 Creating an EVS Disk from a Snapshot (OBT)**.

When a snapshot is no longer needed, delete it according to **9.3 Deleting a Snapshot (OBT)** to release the virtual resources.

Related Operations

For more snapshot FAQs, see **Snapshot FAQs**.

9.2 Creating a Snapshot (OBT)

Scenarios

You can create an EVS snapshot on the management console to save the EVS disk data at a specific time point.

A maximum of 7 snapshots can be created for an EVS disk.

For details about the snapshot principle and application scenarios, see **EVS Snapshot (OBT)**.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

- **Step 3** Switch to the **Create Snapshot** page in either of the following ways:
 - In the disk list, locate the row that contains the target disk, click **More** in the **Operation** column, and choose **Create Snapshot**.

Configure the basic settings for the snapshot according to Table 9-1.

Table 9-1 Parameter description

Parameter	Description	Example Value
Snapshot Name	Mandatory The name can contain a maximum of 64 characters.	snapshot-01

• In the navigation tree on the left, choose **Elastic Volume Service** > **Snapshots**.

On the **Snapshots** page, click **Create Snapshot**.

Configure the basic settings for the snapshot according to Table 9-2.

Table 9-2 Parameter description

Parameter	Description	Example Value
Region	Mandatory	-
	After you select a region, the disks in the selected region will be displayed for you to choose.	
Snapshot	Mandatory	snapshot-01
Name	The name can contain a maximum of 64 characters.	
Select Disk	Mandatory	volume-01
	Select a disk based on which the snapshot is to be created.	

Step 4 Click Next.

Step 5 Return to the **Snapshots** page to view the snapshot creation information.

When the snapshot status changes to **Available**, the creation is successful.

----End

Related Operations

For snapshot creation FAQs, see **Snapshot FAQs**.

9.3 Deleting a Snapshot (OBT)

Scenarios

If a snapshot is no longer used, you can release the virtual resources by deleting the snapshot from the system. Snapshot deletion has the following constraints:

• A snapshot can be deleted only when its status is **Available** or **Error**.

- If a disk is deleted, all the snapshots created for this disk will also be deleted.
- When a backup is created for a disk, the system automatically creates a snapshot, and the snapshot name starts with autobk_snapshot_vbs_. Only the snapshot automatically created during the latest backup is retained. You can only view details of this snapshot but cannot delete it.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.
- **Step 3** In the navigation tree on the left, choose **Elastic Volume Service** > **Snapshots**. The snapshot list page is displayed.
- **Step 4** In the snapshot list, locate the row that contains the target snapshot and click **Delete** in the **Operation** column.
- **Step 5** (Optional) If multiple snapshots are to be deleted, select snapshot and click **Delete** in the upper area of the list.
- **Step 6** In the displayed dialog box, confirm the information and click **Yes**.

If the snapshot is no longer displayed in the snapshot list, the snapshot is deleted successfully.

----End

9.4 Viewing Details of a Snapshot (OBT)

Scenarios

This topic describes how to view the details of a snapshot.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Storage**, click **Elastic Volume Service**.
- **Step 3** In the navigation tree on the left, choose **Elastic Volume Service** > **Snapshots**.

 The snapshot list page is displayed.
- **Step 4** Locate the row that contains the target snapshot and click in front of the snapshot name.

On the details page, view the snapshot information, such as the snapshot size.

9.5 Rolling Back Data from a Snapshot (OBT)

Scenarios

If the data on an EVS disk is incorrect or damaged, you can roll back the data from a snapshot to the source disk to restore data. Snapshot rollback has the following constraints:

- A snapshot can be rolled back only to its source EVS disk. A rollback to another disk is not possible.
- A snapshot can be rolled back only when the snapshot status is Available and the source disk status is Available (not attached to any server) or Rollback failed.
- When a backup is created for a disk, the system automatically creates a snapshot, and the snapshot name starts with autobk_snapshot_vbs_. Only the snapshot automatically created during the latest backup is retained. This snapshot can be viewed only, but cannot be used to roll back the disk data.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.
- **Step 3** In the navigation tree on the left, choose **Elastic Volume Service** > **Snapshots**. The snapshot list page is displayed.
- **Step 4** In the snapshot list, locate the row that contains the target snapshot and click **Roll Back Disk** in the **Operation** column.
- **Step 5** In the displayed dialog box, click **Yes**.
- **Step 6** The snapshot list is displayed. After the snapshot status changes from **Rolling** back to **Available**, the data rollback is successful.

----End

9.6 Creating an EVS Disk from a Snapshot (OBT)

Scenarios

This topic is used to guide users to create an EVS disk from a snapshot. You can select the target snapshot directly in the snapshot list or specify parameter **Create from snapshot** on the disk creation page to create the EVS disk.

When a disk is created from a snapshot, the new disk has the following constraints:

- The disk type of the new disk is the same as that of the snapshot's source disk.
- The device type of the new disk is the same as that of the snapshot's source disk.

- The encryption attribute of the new disk is the same as that of the snapshot's source disk
- A maximum of 128 disks can be created from this snapshot.
- Batch disk creation is not possible, and the quantity parameter must be set to **1**.
- When a backup is created for a disk, the system automatically creates a snapshot, and the snapshot name starts with autobk_snapshot_vbs_. Only the snapshot automatically created during the latest backup is retained. This snapshot can be viewed only, but cannot be used to create new disks.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.
- **Step 3** In the navigation tree on the left, choose **Elastic Volume Service** > **Snapshots**. The snapshot list page is displayed.
- **Step 4** In the snapshot list, locate the row that contains the target snapshot and click **Create Disk** in the **Operation** column.
- **Step 5** Set the disk parameters.

For details, see Purchasing an EVS Disk.

A maximum of 128 disks can be created from a snapshot.

- In the condition that you do not specify the disk capacity, if the snapshot size is smaller than 10 GB, the default capacity 10 GB will be used as the disk capacity; if the snapshot size is greater than 10 GB, the disk capacity will be consistent with the snapshot size.
- To specify a disk capacity larger than the snapshot size, set the disk capacity in the **Disk Specifications** area.
- Step 6 Click Next.
- **Step 7** Pay for the fees as prompted and click **OK**.

The disk list page is displayed.

Step 8 Go back to the disk list page and view the disk status.

When the disk status changes to **Available**, the disk is successfully created.

10 Managing EVS Disk Transfer

Scenarios

Through EVS disk transfer, EVS disks can be transferred from one account to another. After the transfer succeeds, the ownerships of the EVS disks belong to the target account only. Currently, only data disks can be transferred.

Currently, users can use the disk transfer function by making API calls only. For details, see chapter "EVS Disk Transfer" in the *Elastic Volume Service API Reference*.

Constraints

- Encrypted EVS disks cannot be transferred.
- EVS disks with backups and snapshots available cannot be transferred.
- EVS disks associated with backup policies cannot be transferred.
- EVS disks used as system disks cannot be transferred.

Procedure

The following example shows you how to transfer an EVS disk from account A to account B. User A belongs to account A, and user B belongs to account B. User A creates the transfer. User B accepts the transfer through the transfer ID (transfer_id) and authentication key (auth_key). After the transfer has been accepted, the transfer is complete. Figure 10-1 shows the basic transfer process.

- transfer_id specifies the disk transfer ID. Each EVS disk transfer has a transfer ID, and user B uses this ID to accept the disk transfer.
- auth_key specifies the identity authentication key of the disk transfer. Each EVS disk transfer has an authentication key, and user B uses this key for authentication when accepting the disk transfer.




Figure 10-1 Operation procedure (EVS disk transfer)

- **Step 1** User A creates the transfer. For details, see "Creating a Disk Transfer" in the *Elastic Volume Service API Reference*.
 - After the transfer is successfully created, transfer_id and auth_key are returned.
- **Step 2** (Optional) User A can view the disk transfer. For details, see "Querying Details of a Disk Transfer" in the *Elastic Volume Service API Reference*. If multiple disk transfers have been created, user A can query all disk transfers. For details, see "Querying All Disk Transfers" or "Querying Details of All Disk Transfers" in the *Elastic Volume Service API Reference*.
- **Step 3** User A delivers the returned **transfer_id** and **auth_key** to user B.
- **Step 4** Check whether user B is going to accept the disk transfer.
 - If yes, go to **Step 5**.
 - If no, no further action is required.
 User A can delete the unaccepted disk transfer. For details, see Deleting a Disk Transfer.

- **Step 5** User B accepts **transfer_id** and **auth_key**.
- **Step 6** User B accepts the transfer through **transfer_id** and **auth_key**. For details, see **Accepting a Disk Transfer**.

11 Managing a Tag

11.1 Tag Overview

Tags identify EVS resources for purposes of easy categorization and quick search.

Table 11-1 Tag overview

Operation	Scenario
11.2 Adding a Tag	Add tags for existing disks or during disk creations.
11.3 Modifying a Tag	Change tag values for existing disks. Tag keys of existing disks cannot be changed.
11.4 Deleting a Tag	Delete tags that are no longer needed for existing disks.
11.5 Searching Disks by Tags	After tags are added, search for disks by tags.

11.2 Adding a Tag

Scenarios

This topic is used to guide users to add a tag for an existing EVS disk. You can also add tags during the EVS disk creation.

Tags are used to identify the cloud resources for purposes of easy categorization and quick search.

- A tag is composed of a key-value pair.
 - A tag key is a string of no more than 36 characters. It consists of letters, digits, underscores (_), hyphens (-), and Unicode characters (\u4E00-\u9FFF).

- A tag value is a string of no more than 43 characters. It consists of letters, digits, underscores (_), periods (.), hyphens (-), and Unicode characters (\u4E00-\u9FFF).
- A maximum of 10 tags can be added for an EVS disk.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Storage**, click **Elastic Volume Service**.

The disk list page is displayed.

Step 3 In the disk list, locate the target disk and click the disk name.

The disk details page is displayed.

- Step 4 Click the Tags tab.
- Step 5 Click Add Tag.

The **Add Tag** page is displayed.

- **Step 6** Enter a key and a value for a tag and click **OK**.
 - **Key**: This parameter is mandatory.
 - Value: This parameter is optional.

The **Tags** tab is displayed, and you can view the newly added tag.

----End

11.3 Modifying a Tag

Scenarios

You can change the value of a tag for an existing disk, but cannot change the key of a tag.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Storage**, click **Elastic Volume Service**.

The disk list page is displayed.

Step 3 In the disk list, locate the target disk and click on the disk name.

The disk details page is displayed.

- **Step 4** Click the **Tags** tab.
- **Step 5** Locate the target tag and click **Edit** in the **Operation** column.

The **Edit Tag** page is displayed.

Step 6 Change the value of the tag and click **OK**.

Return to the tag list. If the tag value is changed, the modification is complete.

----End

11.4 Deleting a Tag

Scenarios

If an existing tag is no longer needed, you can delete it.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

Step 3 In the disk list, locate the target disk and click on the disk name.

The disk details page is displayed.

- Step 4 Click the Tags tab.
- **Step 5** Locate the target tag and click **Delete** in the **Operation** column.

The **Delete Tag** page is displayed.

Step 6 Confirm the information and click **Yes**.

Return to the tag list. If the tag is no longer displayed in the tag list, the deletion is successful.

----End

11.5 Searching Disks by Tags

Scenarios

Tags can be used to categorize EVS disks, and users can quickly search for their desired EVS disks by tags. This topic is used to guide users to search for EVS disk by existing tags.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** Under **Storage**, click **Elastic Volume Service**.

The disk list page is displayed.

Step 3 In the upper area of the disk list, click **Search by Tag**.

The **Search by Tag** page is displayed.

- **Step 4** Enter or select an existing tag in the text box under **Search by Tag**.
- **Step 5** (Optional) If disks containing multiple tags need to be queried, click to add tags.

A maximum of 10 tags can be added at a time.

For the added tags, you can delete them individually or click **Reset** to clear all of them.

Step 6 After the tags are added, click **Search**.

Disks owning the added tags are displayed in the list, and the search is complete.

12 Changing Disk Name

Scenarios

Disk names are used to identify disks. After a disk is created, you can perform operations in this section to change the disk name if needed.

Constraints

The name of a disk can be changed only when the disk status is **Available** or **Inuse**.

Procedure

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

- **Step 3** Change the disk name in either of the following ways:
 - Perform the following steps to change the disk name in the disk list:
 - a. In the disk list, locate the target disk in the **Disk Name** column and click to the right of the disk name.

The **Edit Disk Name** dialog box is displayed.

- b. Enter a new name.
- c. Click **OK**.

After the change is successful, the new disk name is displayed in the disk list

- Perform the following steps to change the disk name on the disk details page:
 - a. In the disk list, locate the target disk and click the disk name.

 The disk details page is displayed.
 - b. Click $\stackrel{\checkmark}{=}$ next to the disk name.
 - c. Enter a new name.
 - d. Click .

After the change is successful, the new disk name is displayed on the disk details page.

13 Viewing EVS Monitoring Data

Description

This topic describes monitored metrics reported by EVS to Cloud Eye as well as their namespaces and dimensions. You can use console or APIs provided by Cloud Eye to query the metrics of the monitored objects and alarms generated for EVS.

Namespace

SYS.EVS

Metrics

Metric ID	Metric Name	Meaning	Value Range	Monitore d Object	Monitorin g Period (Raw Data)
disk_de vice_re ad_byt es_rate	Disk Read Bandwidt h	Number of bytes read from the monitored disk per second Unit: Bytes/s	≥ 0 bytes/s	EVS disk	5 minutes
disk_de vice_wr ite_byt es_rate	Disk Write Bandwidt h	Number of bytes written to the monitored disk per second Unit: Bytes/s	≥ 0 bytes/s	EVS disk	5 minutes
disk_de vice_re ad_req uests_r ate	Disk Read IOPS	Number of read requests sent to the monitored disk per second Unit: Requests/s	≥ 0 Requests/ s	EVS disk	5 minutes

Metric ID	Metric Name	Meaning	Value Range	Monitore d Object	Monitorin g Period (Raw Data)
disk_de vice_wr ite_req uests_r ate	Disk Write IOPS	Number of write requests sent to the monitored disk per second Unit: Requests/s	≥ 0 Requests/ s	EVS disk	5 minutes
disk_de vice_qu eue_le ngth	Average Queue Length	Average number of read or write requests waiting for processing in the monitoring period for the monitored disk Unit: Count	≥ 0 Counts	EVS disk	5 minutes
disk_de vice_io _util	Disk I/O Utilizatio n	Percentage of time spent during which read and write requests were sent to the monitored disk in the monitoring period Unit: Percent	0-100%	EVS disk	5 minutes
disk_de vice_wr ite_byt es_per_ operati on	Avg Disk Bytes Per Write	Average number of bytes transmitted per I/O write for the monitored disk in the monitoring period Unit: Kbyte/ operation	≥ 0 KB/op	EVS disk	5 minutes
disk_de vice_re ad_byt es_per_ operati on	Avg Disk Bytes Per Read	Average number of bytes transmitted per I/O read for the monitored disk in the monitoring period Unit: Kbyte/ operation	≥ 0 KB/op	EVS disk	5 minutes

Metric ID	Metric Name	Meaning	Value Range	Monitore d Object	Monitorin g Period (Raw Data)
disk_de vice_wr ite_aw ait	Disk Write Await	Average await time per I/O write for the monitored disk in the monitoring period Unit: ms/operation	≥ 0 ms/ operation	EVS disk	5 minutes
disk_de vice_re ad_aw ait	Disk Read Await	Average await time per I/O read for the monitored disk in the monitoring period Unit: ms/operation	≥ 0 ms/ operation	EVS disk	5 minutes
disk_de vice_io _svctm	Disk I/O Service Time	Average service time per I/O read or write for the monitored disk in the monitoring period Unit: ms/operation	≥ 0 ms/ operation	EVS disk	5 minutes
iops_qo s_num	IOPS Upper Limit Reached (Count)	Number of times that the IOPS of the monitored disk has reached the upper limit Unit: Count	≥ 0 Counts	EVS disk	5 minutes
iobw_q os_nu m	Bandwidt h Upper Limit Reached (Count)	Number of times that the bandwidth of the monitored disk has reached the upper limit Unit: Count	≥ 0 Counts	EVS disk	5 minutes

Dimension

Key	Value
disk_name	Server ID-drive letter, for example, 6f3c6f91-4b24-4e1b-b7d1-a94ac1cb011d-sda (sda is the drive letter)

Viewing Monitoring Data

- **Step 1** Log in to the management console.
- Step 2 Under Storage, click Elastic Volume Service.

The disk list page is displayed.

Step 3 In the EVS disk list, click the name of the disk you want to view the monitoring data.

The disk details page is displayed.

Step 4 On the **Servers** tab, locate the row that contains the server and click **View Metric** in the **Operation** column.

The Monitoring metric page is displayed.

Step 5 You can view the disk monitoring data by metric or monitored duration.

14 Querying EVS Traces

Scenarios

EVS supports the recording of EVS operations through CTS. You can query EVS traces and use them for historical operation audits and backtracks.

Prerequisites

CTS has been enabled.

Key EVS Operations Recorded by CTS

Table 14-1 EVS operations that can be recorded by CTS

Operation	Resource Type	Trace Name
Creating an EVS disk	evs	createVolume
Updating an EVS disk	evs	updateVolume
Expanding an EVS disk	evs	extendVolume
Deleting an EVS disk	evs	deleteVolume

Viewing Traces

To query audit logs, see **Querying Real-Time Traces**.

15 Managing Quotas

15.1 Querying EVS Resource Quotas

Scenarios

Quotas are enforced for service resources on the platform to prevent unforeseen spikes in resource usage. Quotas can limit the number or amount of resources available to users, such as the number of EVS disks, the capacity of EVS disks, and the number of EVS snapshots.

Users can perform the following operations to view the resource quota details.

Procedure

- **Step 1** Log in to the management console.
- **Step 2** In the upper right corner of the page, choose **Resources** > **My Quotas**.

The Service Quota page is displayed.

Figure 15-1 My Quotas



Step 3 View the used and total quota of each type of resources on the displayed page.

If a quota cannot meet service requirements, apply for a higher quota.

----End

15.2 Increasing EVS Resource Quotas

Scenarios

Quotas are enforced for service resources on the platform to prevent unforeseen spikes in resource usage. Quotas can limit the number or amount of resources available to users, such as the number of EVS disks, the capacity of EVS disks, and the number of EVS snapshots.

If your resource quotas fail to meet service requirements, perform the following operations to increase quotas.

Procedure

- **Step 1** Log in to the management console.
- Step 2 In the upper right corner of the page, choose Resources > My Quotas.

The Service Quota page is displayed.

Figure 15-2 My Quotas



- Step 3 Click Increase Quota.
- **Step 4** On the **Create Service Ticket** page, configure parameters as required.

 In **Problem Description** area, fill in the content and reason for adjustment.
- Step 5 After all necessary parameters are configured, select I have read and agree to the Tenant Authorization Letter and Privacy Statement and click Submit.



A.1 EVS Disk Status

An EVS disk has several statuses. **Table A-1** lists the EVS disk statuses, the meaning of each status, and the operations a disk in each status allows.

Table A-1 Disk status details

EVS Disk Status	Description	Allowed Operation
In-use	The EVS disk is attached to a server and is in use.	DetachingCreating VBS backupsExpanding
Available	The EVS disk has not been attached to any server and can be attached.	 Attaching Expanding Deleting Creating VBS backups Rolling back snapshots to EVS disks NOTE Currently, you can only roll back a snapshot to an EVS disk by calling the API.
Creating	The EVS disk is being created.	None
Attaching	The EVS disk is being attached to a server.	None

EVS Disk Status	Description	Allowed Operation
Detaching	The EVS disk is being detached from a server.	None
Deleting	The EVS disk is being deleted.	None
Restoring	A backup is being used to restore the EVS disk.	None
Expanding	The capacity of the EVS disk is being expanded.	None
Uploading	Data on the EVS disk is being uploaded to an image. This state occurs when you create an image from a server.	None
Downloadin g	Data is being downloaded from an image to the EVS disk. This state occurs when you create a server.	None
Error	An error occurs when you try to create an EVS disk.	Deleting
Deletion failed	An error occurs when you try to delete the EVS disk.	None
Expansion failed	An error occurs when you try to expand the capacity of the EVS disk.	Deleting
Restoration failed	An error occurs when you try to restore the EVS disk from a backup.	Deleting
Rolling back	Data on the EVS disk is being restored from a snapshot. NOTE When you roll back a snapshot to an EVS disk, you can only roll back the snapshot to the source EVS disk. Rollback to a specified disk is not supported. You can roll back an EVS disk from a snapshot only when the disk is in the Available or Rollback failed state.	None
Rollback failed	An error occurs when the EVS disk is rolled back from a snapshot.	DeletingRolling back snapshots to EVS disks
Awaiting transfer	The EVS disk is awaiting for a transfer.	None

□ NOTE

If an EVS disk status is Error, Deletion failed, Expansion failed, Restoration failed, or Rollback failed, you can rectify the error by following the steps provided in What Can I Do If an Error Occurs on My EVS Disk in FAQs.

A.2 EVS Snapshot Status

An EVS snapshot has several statuses. **Table A-2** lists the EVS snapshot statuses, the meaning of each status, and the operations a snapshot in each status allows.

Table A-2 Snapshot status details

Snapshot Status	Description	Allowed Operation
Creating	The snapshot is being created.	No operations are allowed.
Available	The snapshot is successfully created.	Creating EVS disks using snapshots
		 Deleting snapshots Rolling back snapshots to source EVS disks
Deleting	The snapshot is being deleted.	No operations are allowed.
Error	An error occurs when you try to create a snapshot.	Deleting
Deletion failed	An error occurs when you try to delete a snapshot.	No operations are allowed.
Rolling back	The snapshot is rolling back data. NOTE When you roll back a snapshot to an EVS disk, you can only roll back the snapshot to the source EVS disk. Rollback to a specified disk is not supported. You can roll back an EVS disk from a snapshot only when the disk is in the Available or Rollback failed state.	No operations are allowed.

Snapshot Status	Description	Allowed Operation
Backing up	This status is available only to temporary snapshots. When you create a backup for an EVS disk, a temporary snapshot is automatically created. This status indicates that a temporary snapshot is being created during the backup creation.	No operations are allowed.
	NOTE Temporary snapshots are created through the CBR service. Do not perform any operation on these snapshots.	

B Change History

Release Date	What's New	
2021-01-25	This issue is the ninth official release, which incorporates the following change: • Added Extending Disk Partitions and File Systems (Windows Server 2016).	
2019-06-30	This issue is the eighth official release, which incorporates the following change: Added support for the TMS tag function.	
2018-10-30	 This issue is the seventh official release, which incorporates the following changes: Added Changing Disk Name. Modified the parameter list for purchasing disks according to the modifications made on the console. 	
2018-08-15	This issue is the sixth official release, which incorporates the following changes: • Added support for the EVS snapshot function. • Added support for expanding In-use EVS disks.	
2018-08-03	 This issue is the fifth official release, which incorporates the following changes: Added precautions for using shared EVS disks together with SCSI. Modified disk performance metrics. 	
2018-06-30	This issue is the fourth official release, which incorporates the following change: • Added Managing EVS Disk Transfer.	

Release Date	What's New	
2018-01-22	This issue is the third official release, which incorporates the following changes:	
	Added support for SCSI EVS disks.	
	Added support for shared EVS disks.	
2018-01-15	This issue is the second official release, which incorporates the following change:	
	Made modifications to the document according to changes made on the console.	
2017-12-31	This issue is the first official release.	