



# **Security Center System Requirements**

## **Guide 5.7**

Document last updated: December 15, 2017

# Copyright notice

---

© Genetec Inc., 2017

Genetec Inc. distributes this document with software that includes an end-user license agreement and is furnished under license and may be used only in accordance with the terms of the license agreement. The contents of this document are protected under copyright law.

The contents of this guide are furnished for informational use only and are subject to change without notice. Genetec Inc. assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

This publication may not be copied, modified, or reproduced in any form or for any purpose, nor can any derivative works be created therefrom without Genetec Inc.'s prior written consent.

Genetec Inc. reserves the right to revise and improve its products as it sees fit. This document describes the state of a product at the time of document's last revision, and may not reflect the product at all times in the future.

In no event shall Genetec Inc. be liable to any person or entity with respect to any loss or damage that is incidental to or consequential upon the instructions found in this document or the computer software and hardware products described herein. The use of this document is subject to the disclaimer of liability found in the end-user license agreement.

Genetec, Genetec Clearance, Omnicast, Synergis, AutoVu, Federation, Stratocast, Sipelia, Streamvault, Citywise, Genetec Retail Sense, Genetec Traffic Sense, Genetec Airport Sense, Genetec Motoscan, Genetec Citigraf, Genetec Mission Control, Genetec ClearID, Genetec Patroller, Community Connect, the Genetec Logo, the Mobius Strip Logo, the Genetec Clearance Logo, the Omnicast Logo, the Synergis Logo, the AutoVu Logo, and the Stratocast Logo are trademarks of Genetec Inc., and may be registered or pending registration in several jurisdictions. Other trademarks used in this document may be trademarks of the manufacturers or vendors of the respective products.

All specifications are subject to change without notice.

## **Document information**

Document title: Security Center System Requirements Guide 5.7 SR1

Document number: EN.500.100-V5.7.C1(2)

Document update date: December 15, 2017

You can send your comments, corrections, and suggestions about this guide to [documentation@genetec.com](mailto:documentation@genetec.com).

# Security Center System Requirements

This section includes the following topics:

- ["Security Center 5.7 client workstation requirements"](#) on page 2
- ["Maximum number of cameras viewed per client type"](#) on page 3
- ["Security Center 5.7 server requirements"](#) on page 4
- ["Maximum number of cameras and readers per server type"](#) on page 5
- ["Security Center 5.7 AutoVu LPR server requirements"](#) on page 7
- ["Security Center 5.7 software requirements"](#) on page 8
- ["Additional considerations for server specifications in Security Center 5.7"](#) on page

10

## Security Center 5.7 client workstation requirements

To ensure that your client workstation runs optimally, it's important to know the minimum, recommended, and high performance requirements for a Security Center 5.7 client workstation.

The requirements for Security Center 5.7 client workstations are as follows:

Client profile	Client characteristics
<b>Minimum</b>	<ul style="list-style-type: none"> <li>• Intel® Core™ 2 X6800 @ 2.93 GHz</li> <li>• 2 GB of RAM or better</li> <li>• 80 GB hard drive for OS and Security Center applications</li> <li>• 256 MB PCI-Express x16 video card</li> <li>• 1280 x 1024 or higher screen resolution with 96 dpi</li> <li>• 100 Mbps Ethernet network interface card</li> </ul>
<b>Recommended</b>	<ul style="list-style-type: none"> <li>• 4<sup>th</sup> Generation Intel® Core™ i7-4770 or better</li> <li>• 8 GB of RAM or better</li> <li>• 64-bit operating system</li> <li>• 120 GB Solid State Drive for OS and Security Center applications</li> <li>• GbE network interface card</li> <li>• NVIDIA® QUADRO K620 2 GB video card</li> </ul>
<b>High performance</b> <i>Video intensive configuration</i>	<ul style="list-style-type: none"> <li>• 4<sup>th</sup> Generation Intel® Core™ i7-4770 or better</li> <li>• 16 GB of RAM or better</li> <li>• 64-bit operating system</li> <li>• 240 GB Solid State Drive for OS and Security Center applications</li> <li>• GbE network interface card</li> <li>• 1 x NVIDIA® GeForce® GTX 1060 6 GB video card</li> </ul>

### GPU considerations

- Minimum of 2 GB of video RAM recommended.
- If your Intel® processors support Intel® Quick Sync Video, then this technology can also be used provided the monitor is plugged into the motherboard. Laptops can also use Quick Sync Video.
- Two or more graphic cards can be used to support different monitors individually. To have the video decoding done on the card, at least one monitor must be connected to each card.
- NVIDIA® SLI™ bridge not supported.
- The decoding of H.265 HEVC video can be accelerated using an NVIDIA® GeForce® GTX 1060, GTX 1070, or GTX 1080 video card.

## Maximum number of cameras viewed per client type

To ensure that your client workstation runs optimally, it is important to know the maximum number of cameras that can be viewed per client workstation type in Security Center 5.7.

The maximum number of cameras viewed per client workstation type in Security Center 5.7 are as follows:

H.264 format	CIF	VGA	HD	Full HD	Ultra HD
Resolution @ 30 fps	352 x 240	640 x 480	1280 x 720	1920 x 1080	3840 x 2160
Average bit rate/camera <sup>1</sup>	350 Kbps	1 100 Kbps	2 300 Kbps	5 500 Kbps	50 000 Kbps
<b>Minimum</b>	14	6	2	1	0
<b>Recommended<sup>2</sup></b>	60	47	23	11	6
<b>High performance<sup>2,3</sup></b> <i>Video intensive configuration</i>	78	58	50	26	8

<sup>1</sup> These are estimates, and different camera manufacturer's bit rate may vary with the same resolution and frame rate. The decoding performance can also vary from one manufacturer to another.

<sup>2</sup> With hardware acceleration enabled.

<sup>3</sup> Using one video card NVIDIA<sup>®</sup> GeForce GTX 1060 with 6 GB of RAM

### Performance benchmark for HEVC (H.265)

The following benchmark illustrates the average bit rate of a camera streaming at 20 fps using HEVC (H.265) video format.

The viewing workstation has a 4<sup>th</sup> Generation Intel<sup>®</sup> Core™ i7-4770 @ 3.5 GHz processor, with 16 GB RAM, an SSD hard drive, and runs Windows 8.1. The video card used is an NVIDIA<sup>®</sup> GeForce<sup>®</sup> GTX 1060 with 6 GB of RAM connected to a 4K monitor.

H.265 format	VGA	HD	UXGA	Full HD
Resolution @ 20 fps	640 x 480	1280 x 720	1600 x 1200	1920 x 1080
Average bit rate/camera	115 Kbps	445 Kbps	730 Kbps	3 000 Kbps
<b>Max. number of cameras</b>	77	51	31	24

### Encryption impact on workstation performance

Video encryption can increase the CPU usage by up to 40% when viewing low resolution video (CIF). The impact becomes less noticeable as the resolution of the video increases, because much more processing power is spent on decoding the video than on decrypting the video. The impact on performance becomes unnoticeable when viewing HD and Ultra-HD video.

## Security Center 5.7 server requirements

To ensure that your system runs optimally, it's important to know the minimum, recommended, and high performance server requirements for a Security Center 5.7 Directory, Archiver, and Access Manager.

The requirements for Security Center 5.7 servers are as follows:

Server profile	Server characteristics
<b>Minimum</b>	<ul style="list-style-type: none"> <li>• Intel® Core™ 2 Duo E6850 3.0 GHz or better</li> <li>• 4 GB of RAM or better</li> <li>• 80 GB hard drive for OS and Security Center applications</li> <li>• 32-bit operating system</li> <li>• 100/1000 Mbps Ethernet network interface card</li> <li>• Standard SVGA video card<sup>1</sup></li> </ul>
<b>Recommended</b>	<ul style="list-style-type: none"> <li>• Quad Core Intel® Xeon® E5-2620 v4 2.10 GHz or better</li> <li>• 16 GB of RAM or better</li> <li>• 64-bit operating system</li> <li>• 80 GB SATA II hard drive or better for OS and Security Center applications</li> <li>• GbE network interface card</li> <li>• Standard SVGA video card<sup>1</sup></li> </ul>
<b>High performance</b> <sup>2</sup> <i>Video intensive configuration</i>	<ul style="list-style-type: none"> <li>• <b>Streamvault™ rackmount appliance</b></li> </ul> <p>The Streamvault™ 2000, 4000, and 7000 Series offer high performance for video intensive archiving. Starting from 500 cameras or 500 Mbps, and 150 Mbps of video redirection, up to 1000 cameras or 2000 Mbps, and 400 Mbps of video redirection.</p> <p>To find the right Streamvault™ model for your project, contact Genetec™ Sales at <a href="mailto:sales@genetec.com">sales@genetec.com</a>, or call 1-866-684-8006 (option #2).</p>

<sup>1</sup> Config Tool requires a minimum resolution of 1024 x 768. Not required for virtual servers.

<sup>2</sup> The intended throughput requires specific hardware and software configurations.

## Maximum number of cameras and readers per server type

To ensure that your system runs optimally, it's important to know the maximum number of cameras and readers per server type in Security Center 5.7.

Server type	Minimum	Recommended
<b>Directory &amp; Archiver</b> (Video only)	50 cameras or 50 Mbps	100 cameras or 200 Mbps
<b>Standalone Archiver</b> (Video only)	75 cameras or 75 Mbps	300 cameras or 300 Mbps <sup>1</sup>
<b>Directory &amp; Access Manager</b> (Access control only)	100 HID Edge readers/ V2000, or 150 readers on HID V1000/Synergis™ Cloud Link 10 HID V1000/Synergis™ Cloud Link 10,000 cardholders	300 HID Edge readers/V2000, or 300 readers on HID V1000 or 1024 readers on Synergis™ Cloud Link 100 HID V1000/Synergis™ Cloud Link 250,000 cardholders
<b>Standalone Access Manager</b> (Access control only)	100 HID Edge readers/ V2000, or 150 readers on HID V1000/Synergis™ Cloud Link 10 HID V1000/Synergis™ Cloud Link 10,000 cardholders	700 HID Edge readers/V2000, or 500 readers on HID V1000 or 2048 readers on Synergis™ Cloud Link 100 HID V1000/Synergis™ Cloud Link 250,000 cardholders
<b>Directory, Archiver &amp; Access Manager</b> (Unified)	50 cameras or 50 Mbps and 64 readers 5 HID V1000/Synergis™ Cloud Link 5,000 cardholders	100 cameras or 200 Mbps and 200 readers 40 HID V1000/Synergis™ Cloud Link 40,000 cardholders

<sup>1</sup> For high performance Archivers (500 cameras and up), see [Security Center 5.7 server requirements](#) on page 4.

### Encryption impact on Archiver performance

The first encryption certificate enabled on the Archiver will reduce the capacity of the Archiver by 30%. Each additional encryption certificate applied to all cameras further reduces the Archiver capacity by 4%.

Example: On an Archiver that supports 300 cameras without encryption:

Number of certificates enabled	Number of supported cameras
0 encryption certificates (no encryption)	300 cameras
1 encryption certificate	210 cameras
5 encryption certificates	178 cameras

Number of certificates enabled	Number of supported cameras
10 encryption certificates	145 cameras
20 encryption certificates	96 cameras

**BEST PRACTICE:** Do not exceed 20 encryption certificates per Archiver.

For more information on fusion stream encryption, see the *Security Center Administrator Guide*.

### Privacy protection impact on performance

**CAUTION:** Ensure that the Privacy Protector role is not on the same server as the Archiver because it can affect the CPU performance and the archives. When the CPU usage is high on the Archiver server, *Archiving queue full* situations can occur and data can be lost.

**BEST PRACTICE:** Use an Intel® CPU that supports Intel® Quick Sync Video (such as Intel® Xeon® Processor E3 v5 Family).



## Security Center 5.7 AutoVu™ LPR server requirements

To ensure that your system runs optimally, it's important to know the minimum, recommended, and high performance requirements for a Security Center 5.7 AutoVu™ LPR server.

The requirements for Security Center 5.7 AutoVu™ LPR servers are as follows:<sup>1</sup>

Server profile	Server characteristics
<b>Minimum<sup>2</sup></b>	<ul style="list-style-type: none"> <li>• Intel® Quad Core™ i5-3550 processor equivalent or better (6000 CPU Mark or better)</li> <li>• 12 GB of RAM (minimum 4 GB dedicated to SQL Server)</li> <li>• Separated storage disk from OS primary disk</li> <li>• 50 AutoVu™ units (Sharp or Genetec Patroller™ combined)</li> <li>• SQL Express database server containing up to 6 000 000 LPR Events (Reads and Hits combined)</li> <li>• Maximum of 5 simultaneous user connections</li> </ul>
<b>Recommended</b>	<ul style="list-style-type: none"> <li>• Intel® Quad Core™ i7-3820 processor equivalent or better (8000 CPU Mark or better)</li> <li>• 16 GB of RAM (minimum 6 GB dedicated to SQL Server)</li> <li>• Dedicated RAID5 storage with 4 enterprise grade disks or better</li> <li>• 100 AutoVu™ units (Sharp or Genetec Patroller™ combined)</li> <li>• SQL Standard database server containing up to 25 000 000 LPR Events (Reads and Hits combined)</li> <li>• Maximum of 20 simultaneous user connections</li> </ul>
<b>High performance</b>	<ul style="list-style-type: none"> <li>• Intel® Xeon Quad Core™ processor equivalent or better than E5-1620 v4 (10 000 CPU Mark or better)</li> <li>• 32 GB of RAM (minimum 8 GB dedicated to SQL Server)</li> <li>• Dedicated RAID5 storage with at least 8 high performance enterprise grade disks or better</li> <li>• Up to 250 AutoVu™ units (Sharp or Genetec Patroller™ combined)</li> <li>• SQL Standard database server containing up to 80 000 000 LPR Events (Reads and Hits combined)</li> <li>• Maximum of 80 simultaneous user connections</li> </ul>

<sup>1</sup> These requirements are for installation on a single server. For higher performance, you can distribute the load on several servers.

<sup>2</sup> SV-32 v2 equivalent machine.

## Security Center 5.7 software requirements

To ensure that your system runs optimally, it is important to know the software requirements for Security Center 5.7.

The requirements for Security Center 5.7 software are as follows:

Category	Supported software
<b>Operating systems</b>	<ul style="list-style-type: none"> <li>• Microsoft® Windows 7 Pro/Enterprise/Ultimate SP1<sup>1</sup></li> <li>• Microsoft® Windows 8.1 Pro/Enterprise<sup>1</sup></li> <li>• Microsoft® Windows 10 version 1511 and later<sup>1</sup></li> <li>• Microsoft® Windows 10 Enterprise LTSC</li> <li>• Microsoft® Windows Server 2008 R2 SP1<sup>2,3</sup></li> <li>• Microsoft® Windows Server 2012<sup>2,3</sup></li> <li>• Microsoft® Windows Server 2012 R2<sup>2,3</sup></li> <li>• Microsoft® Windows Server 2016<sup>2,3</sup></li> </ul>
<b>Database Engines</b>	<ul style="list-style-type: none"> <li>• SQL Server 2008 R2 Express/Standard/Enterprise</li> <li>• SQL Server 2012 Express/Standard/Enterprise</li> <li>• SQL Server 2014 Express/Standard/Enterprise</li> <li>• SQL Server 2016 Express/Standard/Enterprise<sup>3</sup></li> </ul>
<b>Browsers for Security Center Server Admin</b>	<ul style="list-style-type: none"> <li>• Internet Explorer 9, 10, and 11</li> <li>• Chrome 46 (or later)</li> <li>• Firefox 42 (or later)</li> <li>• Safari 9 (or later)</li> <li>• Microsoft® Edge 25 (or later)</li> </ul>
<b>Browsers for Synergis™ Appliance Portal</b>	<ul style="list-style-type: none"> <li>• Internet Explorer 9, 10, or Google Chrome</li> </ul>
<b>Browsers for Web Client 5.7</b>	<ul style="list-style-type: none"> <li>• Internet Explorer 11 or higher</li> <li>• Edge for Windows 10</li> <li>• Chrome</li> <li>• Firefox</li> <li>• Safari (desktop version)</li> </ul>

Category	Supported software
<b>Virtualization (Server)</b>	<ul style="list-style-type: none"> <li>• VMware ESXi 5.x</li> <li>• VMware ESXi 6.x</li> <li>• Microsoft<sup>®</sup> Hyper-V with Windows Server 2012/2012 R2/2016 and SQL Server 2016</li> </ul>
<b>Clustering</b>	<ul style="list-style-type: none"> <li>• Microsoft<sup>®</sup> Windows Server 2008/2008 R2/2012/2012 R2</li> <li>• NEC ExpressCluster X R3 WAN/LAN Editions for Windows v.3.0.0.1</li> </ul>

<sup>1</sup> Both 64 and 86 bit versions are supported.

<sup>2</sup> Only Standard, Enterprise, and Datacenter Editions are supported.

<sup>3</sup> Only 64 bit versions are supported.

## Additional considerations for server specifications in Security Center 5.7

---

To ensure your system runs optimally, there are additional things to consider for server specifications in Security Center 5.7.

Note the following additional considerations for server specifications in Security Center 5.7.

- When video streaming is not in multicast from the camera, the maximum throughput calculation must include camera streams being redirected by the Archiver.
- Software-based motion detection can reduce the maximum capacity by as much as 50%. When enabling motion detection, use unit-based motion detection to ensure maximum capacity.
- Systems above 300 cameras or doors must isolate the Directory on a dedicated server.
- A more powerful server than the high end specification will not necessarily increase the maximum capacity.
- A virtual machine with the exact same specifications as its physical counterpart has 20% less capacity.
- A dedicated Network Interface Card (NIC) should be assigned per instance of the Archiver role when using virtualization.
- VMware ESXi must be installed on a clean computer; that is, no operating system is installed on the computer.
- Genetec™ Server cannot be installed on the same machine as the domain controller.

# Where to find product information

You can find our product documentation in the following locations:

- **Genetec™ Technical Information Site:** The latest documentation is available on the Technical Information Site. To access the Technical Information Site, log on to [Genetec™ Portal](#) and click [Technical Information](#). Can't find what you're looking for? Contact [documentation@genetec.com](mailto:documentation@genetec.com).
- **Installation package:** The Installation Guide and Release Notes are available in the Documentation folder of the installation package. These documents also have a direct download link to the latest version of the document.
- **Help:** Security Center client and web-based applications include help, which explain how the product works and provide instructions on how to use the product features. Genetec Patroller™ and the Sharp Portal also include context-sensitive help for each screen. To access the help, click **Help**, press F1, or tap the ? (question mark) in the different client applications.

# Technical support

Genetec™ Technical Assistance Center (GTAC) is committed to providing its worldwide clientele with the best technical support services available. As a customer of Genetec Inc., you have access to the Genetec™ Technical Information Site, where you can find information and search for answers to your product questions.

- **Genetec™ Technical Information Site:** Find articles, manuals, and videos that answer your questions or help you solve technical issues.

Before contacting GTAC or opening a support case, it is recommended to search the Technical Information Site for potential fixes, workarounds, or known issues.

To access the Technical Information Site, log on to [Genetec™ Portal](#) and click [Technical Information](#). Can't find what you're looking for? Contact [documentation@genetec.com](mailto:documentation@genetec.com).

- **Genetec™ Technical Assistance Center (GTAC):** Contacting GTAC is described in the Genetec™ Lifecycle Management (GLM) documents: [EN\\_GLM\\_ASSURANCE](#) and [EN\\_GLM\\_ADVANTAGE](#).

## Additional resources

If you require additional resources other than the Genetec™ Technical Assistance Center, the following is available to you:

- **Forum:** The Forum is an easy-to-use message board that allows clients and employees of Genetec Inc. to communicate with each other and discuss many topics, ranging from technical questions to technology tips. You can log in or sign up at <https://gtapforum.genetec.com>.
- **Technical training:** In a professional classroom environment or from the convenience of your own office, our qualified trainers can guide you through system design, installation, operation, and troubleshooting. Technical training services are offered for all products and for customers with a varied level of technical experience, and can be customized to meet your specific needs and objectives. For more information, go to <http://www.genetec.com/support/training/training-calendar>.

## Licensing

- For license activations or resets, please contact GTAC at <https://gtap.genetec.com>.
- For issues with license content or part numbers, or concerns about an order, please contact Genetec™ Customer Service at [customerservice@genetec.com](mailto:customerservice@genetec.com), or call 1-866-684-8006 (option #3).
- If you require a demo license or have questions regarding pricing, please contact Genetec™ Sales at [sales@genetec.com](mailto:sales@genetec.com), or call 1-866-684-8006 (option #2).

## Hardware product issues and defects

Please contact GTAC at <https://gtap.genetec.com> to address any issue regarding Genetec™ appliances or any hardware purchased through Genetec Inc.